

N O T I C E

THIS DOCUMENT HAS BEEN REPRODUCED FROM
MICROFICHE. ALTHOUGH IT IS RECOGNIZED THAT
CERTAIN PORTIONS ARE ILLEGIBLE, IT IS BEING RELEASED
IN THE INTEREST OF MAKING AVAILABLE AS MUCH
INFORMATION AS POSSIBLE



National Aeronautics and
Space Administration

NASA CR-

160562

JSC-16466

MAR 11 1980

Lyndon B. Johnson Space Center
Houston, Texas 77058

EARTH OBSERVATIONS DIVISION

SPACE AND LIFE SCIENCES DIRECTORATE

"AS-BUILT" DESIGN SPECIFICATION
FOR
CLASSY, AN ADAPTIVE MAXIMUM LIKELIHOOD CLUSTERING METHOD

Job Order 76-662

Prepared By
Lockheed Engineering and Management Services Company, Inc.
Systems and Services Division
Houston, Texas

Contract NAS 9-15800

(NASA-CR-160562) AS BUILT DESIGN
SPECIFICATION FOR CLASSY, AN ADAPTIVE
MAXIMUM LIKELIHOOD CLUSTERING METHOD
(Lockheed Engineering and Management)
HC A06/MF A01

N80-21998

101 p
CSCL 09B G3/61 16768
Unclas

February 1980



LEMSCO-14546

1. Report No. JSC-16466		2. Government Accession No.		3. Recipient's Catalog No.	
4. Title and Subtitle "As-Built" Design Specification for CLASSY, an Adaptive Maximum Likelihood Clustering Method				5. Report Date February 1980	
				6. Performing Organization Code SF3	
7. Author(s) C. L. Horton and R. K. Lennington				8. Performing Organization Report No. LEMSCO-14546	
9. Performing Organization Name and Address Lockheed Engineering & Management Services Company, Inc. Systems and Services Division Houston, Texas 77058				10. Work Unit No.	
				11. Contract or Grant No. 9-15800	
12. Sponsoring Agency Name and Address National Aeronautics and Space Administration Lyndon B. Johnson Space Center Houston, Texas 77058 (J. Sulester, Tech. Monitor)				13. Type of Report and Period Covered User Guide	
				14. Sponsoring Agency Code	
15. Supplementary Notes					
16. Abstract This document contains the description of the latest modifications to the CLASSY System and the associate postprocessor MAXLABEL.					
17. Key Words (Suggested by Author(s))				18. Distribution Statement	
19. Security Classif. (of this report) Unclassified		20. Security Classif. (of this page) Unclassified		21. No. of Pages 63	22. Price*

*For sale by the National Technical Information Service, Springfield, Virginia 22161

JSC- 16466

"AS-BUILT" DESIGN SPECIFICATION
FOR
CLASSY, AN ADAPTIVE MAXIMUM LIKELIHOOD CLUSTERING METHOD

Job Order 76-662


Prepared By


C. L. Horton
R. K. Lennington

Approved By

LEMSCO

JSC

 2-19-80
J. I. Morrow, Supervisor
Software Section

 2/26/80
J. M. Sulester, Technical
Monitor Systems & Facilities
Branch

Prepared By

Lockheed Engineering and Management Services Company, Inc.

For

Earth Observations Division
Space and Life Sciences Directorate

NATIONAL AERONAUTICS AND SPACE ADMINISTRATION
LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS 77058

February 1980

LEMSCO-14546

CONTENTS

Section	Page
1. SCOPE	1-1
2. APPLICABLE DOCUMENTS	2-1
3. SYSTEM DESCRIPTION	3-1
3.1 <u>HARDWARE DESCRIPTION</u>	3-12
3.2 <u>EXEC FILES</u>	3-12
3.2.1 CLASSY EXEC FILES	3-12
3.2.2 DOT DATA EXEC FILE	3-12
3.2.3 IMAGE AND MAXLABEL EXEC	3-13
3.3 <u>CONTROL CARDS</u>	3-14
3.3.1 CLASSY CONTROL CARDS.	3-14
3.3.2 LABEL CONTROL CARDS	3-16
3.4 <u>SOFTWARE DESCRIPTION</u>	3-18
3.4.1 CLASSY SUBROUTINES MODIFIED	3-18
3.4.1.1 SOFTWARE COMPONENT NO. 1 (CLINIT)	3-18
3.4.1.2 SOFTWARE COMPONENT NO. 2 (SETUP9)	3-19
3.4.1.3 SOFTWARE COMPONENT NO. 3 (STATIS)	3-21
3.4.1.4 SOFTWARE COMPONENT NO. 4 (CLPR)	3-23
3.4.2 CLASSY SUBROUTINE ADDED	3-25
3.4.2.1 SOFTWARE COMPONENT NO. 1 (CALRPR)	3-25
3.4.3 IMAGE PROCESSOR AND SUBROUTINES	3-27
3.4.3.1 SOFTWARE COMPONENT NO. 1 (IMAGE).	3-27
3.4.3.2 SOFTWARE COMPONENT NO. 2 (SETUPM)	3-28
3.4.3.3 SOFTWARE COMPONENT NO. 3 (KREDTP)	3-29

Section	Page
3.4.4 MAXLABEL SUBROUTINES.	3-31
3.4.4.1 SOFTWARE COMPONENT NO. 1 (MAXLABEL)	3-31
3.4.4.2 SOFTWARE COMPONENT NO. 2 (SETUPM)	3-33
3.4.4.3 SOFTWARE COMPONENT NO. 3 (READCC)	3-33
3.4.4.4 SOFTWARE COMPONENT NO. 4 (ALLPXI)	3-34
3.4.4.5 SOFTWARE COMPONENT NO. 5 (BAPLS)	3-36
3.4.4.6 SOFTWARE COMPONENT NO. 6 (PRTELB)	3-38
3.4.4.7 SOFTWARE COMPONENT NO. 7 (PRTBAP)	3-39
3.4.4.8 SOFTWARE COMPONENT NO. 8 (PRTAP)	3-41
3.4.4.9 SOFTWARE COMPONENT NO. 9 (PRTAP2)	3-43
3.4.4.10 SOFTWARE COMPONENT NO. 10 (WRTLNS)	3-45
3.4.4.11 SOFTWARE COMPONENT NO. 11 (LNBAP)	3-47
3.4.4.12 SOFTWARE COMPONENT NO. 12 (PXLIN)	3-49
3.4.4.13 SOFTWARE COMPONENT NO. 13 (GETCC)	3-51
3.4.4.14 SOFTWARE COMPONENT NO. 14 (DOTSQK)	3-52
3.4.4.15 SOFTWARE COMPONENT NO. 15 (PAGE)	3-54
4. OPERATION.	4-1

Figures

Figure	Page
System Flow Chart.	3-3
CLASSY EXEC File	3-4
Sample CLASSY Control Card File.	3-5
Sample CLASSY Execution.	3-6
CLASSYN EXEC File.	3-7
DOT EXEC File.	3-8
Sample DOT Control Card File	3-9
Sample DOT Execution	3-9
LABEL EXEC File.	3-10
Sample LABEL Control Card File	3-11
Sample IMAGE and LABEL Execution	3-11

1. SCOPE

This specification establishes the modifications to the CLASSY program as specified in IDSD Category 1 Job Order Task Agreement, titled CLASSY Program Modification. This modification includes the CLASSY post-processor MAXLABEL and its associated program IMAGE.

2. APPLICABLE DOCUMENTS

The following documents form a part of this specification:

J. O. 76-662 Task Agreement titled: CLASY Program Modification

Technical Memorandum Mathematical Description and Program Documentation for CLASSY, An Adaptive Maximum Likelihood Clustering Method, by R. K. Lennington and M.E. Rassbach Elogic, Inc. Houston, Texas.

Earth Observations Division Version of the Laboratory for Applications of Remote Sensing System (EOD-LARSYS) User Guide for the IBM 370/148 Volumn II - User's Reference Manual.

3. SYSTEM DESCRIPTION

The CLASSY clustering algorithm serves to estimate the component distributions which make up the overall mixture distribution of the data. The present software uses the statistics for these component distributions (clusters) along with a set of labelled data vectors to produce maximum likelihood estimates of the proportion of each labelled class associated with each cluster. These estimates (called betas) are obtained through a fixed point iteration procedure. The estimated betas are used to obtain two different estimates of the proportion of each labelled class in the whole scene. In addition labelled cluster maps are produced for the whole scene using two different techniques.

The maximum Likelihood System of programs consists of the following four programs: CLASSY, DOT, IMAGE and LABEL. (Figure 3-1).

The CLASSY Program creates statistically meaningful clusters from the pixels in a selected area of the segment image tape. The program options are defined in a control card file. The cluster statistical parameters for each iteration are saved on the CLASSY Cluster Statistical Parameter Files for later use by the LABEL program and a CLASSY One Channel Unlabelled Cluster Map is optionally written to tape for use by the Accuracy Assessment Programs. Cluster maps are written at the end of the last iteration and optionally written after each iteration (Figures 3-1 and 3-2).

The DOT program creates a Ground Truth Selected Pixel Values and Names File associated with pixel radiance values from the same segment image tape used by CLASSY, the Ground Truth Description File and the program options as defined on the Dot Control Card File. (Figures 3-1 and 3-5).


The IMAGE program creates a Selected Pixel File from the same segment image tape used by CLASSY and DOT. The LABEL Control Card File is used to define the options. (Figures 3-1 and 3-9).

The LABEL program processes the CLASSY Cluster Statistical Parameter File from CLASSY, the Ground Truth Selected Pixel Values and Name File from DOT and the Selected Pixel File from IMAGE to create a One Channel Labelled Cluster Map on tape for use by the Accuracy Assessment Programs and the six following reports:

- Iteration Report
- Pixel Labelled Dot Map
- Unlabelled Dot Map
- Entropy and Posterior Probability for each Cluster Report
- Pixel Labelled Cluster Map
- Cluster Labelled Map

Processing Order -- EXECs: CLASSY or CLASSYN
 PROGRAMS: CLASSY
 DOT
 IMAGE and LABEL

SYSTEM FLOW CHART



>type classu exec

ORIGINAL PAGE IS
OF POOR QUALITY

CLASSY EXEC FILE

```
GLOBAL TXLIB FORTRAN CMLIB
$IF $STORAGE GE 2048 $SKIP 2
$TYPE DFF STUR 2M REQUIRED
$EXIT
$IF $INDEX EQ 2 $SKIP 3
$IF $3 EQ 1 $SKIP 3
$SK = $2 - 1
TAPE FSF $SK
$CONTROL OFF
GETDISK JSC770 191 350 R B/A PASS AUCOIN
$SLEEP = 1
-GET GETDISK TEMP 3M CLEAR DETACH
$IF $RETCODE EQ 0 $SKIP 7
$IF $SLEEP LE 7 $SKIP 3
$TYPE NO 25 CYL TEMP DISK AVAILABLE
CP 0 T
$EXIT
CP SLEEP 5 MIN
$SLEEP = $SLEEP + 1
$GOTO -GET
0 DISK 0
GETDISK LARSYS
FILEDEF FT02F001 DISK FILE FT02F001 A1 (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT02F002 DISK FILE FT02F002 A1 (LRECL 320 BLKSIZE 320 PERM
FILEDEF 3 TERM (PERM
FILEDEF FT04F001 DISK FILE FT04F001 A4 (LRECL 3060 BLKSIZE 3060 PERM
FILEDEF FT04F002 DISK FILE FT04F002 A4 (LRECL 3060 BLKSIZE 3060 PERM
FILEDEF FT04F003 DISK FILE FT04F003 A4 (LRECL 3060 BLKSIZE 3060 PERM
FILEDEF 6 DISK OUT6 LISTING U (PERM
FILEDEF FT09F001 DISK FILE FT09F001 A1 (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT11F001 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F002 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F003 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F004 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F005 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F006 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F007 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F008 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F009 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F010 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F011 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F012 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F013 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F014 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F015 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F016 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F017 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F018 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F019 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F020 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F021 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F022 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F023 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F024 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F025 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F026 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F027 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F028 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F029 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F030 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT12F001 TAP2 (BLKSIZE 3060 RECFM U DEN 800 PERM
FILEDEF FT12F002 TAP2 (BLKSIZE 12356 RECFM U DEN 800 PERM
FILEDEF FT13F001 DISK FILE FT13F001 A4 (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT14F001 DISK FILE FT14F001 D1 (LRECL 3060 BLKSIZE 3060 PERM
FIL FT16F001 DISK FILE FT16F001 A1 (LRECL 3060 RECFM U BLKSIZE 3060 PERM
FILEDEF FT17F001 TAP3 (BLKSIZE 12356 RECFM U DEN 800 PERM
FILEDEF FT19F001 DISK FILE FT19F001 A1 (LRECL 1860 BLKSIZE 1860 PERM
FILEDEF FT19F002 DISK FILE FT19F002 A1 (LRECL 1860 BLKSIZE 1860 PERM
FILEDEF FT20F001 DISK FILE FT20F001 A4 (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT20F002 DISK FILE FT20F002 A4 (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT21F001 DISK $1 CC A1 (LRECL 80 BLKSIZE 800 PERM
FILEDEF FT21F002 DISK FILE FT21F002 A1 (LRECL 80 BLKSIZE 800 PERM
FILEDEF 22 DISK FILE FT22F001 D (LRECL 800 BLKSIZE 800 XTENT 2100 PERM
FIL FT23F001 DISK $1 1 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FIL FT23F002 DISK $1 2 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FIL FT23F003 DISK $1 3 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FIL FT23F004 DISK $1 4 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FIL FT23F005 DISK $1 5 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FILEDEF 26 DISK FILE MEANS A (PERM
LOAD CLASY BLKCLA (CLEAR START NOMAP
REMOTE E TO HOUSTON
SPOOL E HOLD
PRINT OUT6 LISTING D
$IF $INDEX LT 4 $SKIP 10
CP DET 101
TAPMOUNT $4 TAP1 RI
$IF $INDEX NE 5 $SKIP 3
$IF $5 EQ 1 $SKIP 2
$SP = $5 - 1
TAPE FSF $SP
FIL INMOVE DISK FILE FT16F001 A (BLKSIZE 3060 RECFM U PERM
FIL OUTMOVE TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
MOVFILE
TAPL WITH 2
CP DET 101
```

>TYPE 1394 CC A

SAMPLE CLASSY CONTROL CARD FILE

COMMENT CLASSY RUN ON SEGMENT 1394
CHANNELS 1,2,3,4,5,6,7,8
DATAFILE FILE=1
ITER 5
MAP 5
LINES 1-117
NPTS 2
SEGM 1394
PROC 30,1,80
TIME 150

END

(1,1), (1,1), (196,1), (196,117), (1,117)

\$END*

>def stor 2n
STORAGE = 02048K
R: T=0.01/0.01 10:45:37

SAMPLE CLASSY EXECUTION of Segment 1394

>classy 1394 5123 1
GLOBAL TXTLIB FORTRAN CHSLIB
JSC770 191 HAS BEEN ATTACHED AS 350.
B (350) R/O
350 HAS BEEN LOGGED IN AS B/A DISK.
DASD 192 DETACHED
YOU ALREADY HAD A VIRTUAL DEVICE 192. IT IS BEING DETACHED.
TEMP 157 HAS BEEN ATTACHED AS 192. (003.00 MEGABYTES)
192 HAS BEEN LOGGED IN AS D DISK.
D (192): 0 FILES; 4 REC IN USE; 3720 LEFT (of 3724), 0% FULL (14 CYL), 3330, R/W
LARS LIB 29C HAS BEEN ATTACHED AS 19C.
Y (19C) R/O
19C HAS BEEN LOGGED IN AS Y DISK.
EXECUTION BEGINS...

CLASY STARTED
PROPORTION RELATIVE TO TOP LEVEL = 1.000000 1
00-00
01-00
02-45 03-55

PROPORTION RELATIVE TO TOP LEVEL = 1.000000 1
PROPORTION RELATIVE TO TOP LEVEL = 0.750047 2
PROPORTION RELATIVE TO TOP LEVEL = 1.000000 1
INDEX = 2 SYMBOL = *****
KL=*** INDEX(KL)= 2 NUMBER= 2 RELPR= 0.0 0.0
PROPORTION RELATIVE TO TOP LEVEL = 0.816835 2
00-00
01-00
02-82 03-18
04-37 05-45

PROPORTION RELATIVE TO TOP LEVEL = 1.000000 1
0***SEPERATE 1 SUPER,SUBS 0 2 SPFAC 0.18557E 02
00-00
02-82 03-18
04-37 05-45

PROPORTION RELATIVE TO TOP LEVEL = 0.830760 2
PROPORTION RELATIVE TO TOP LEVEL = 0.484035 5
00-00
02-82 03-16
04-34 05-48
06-24 07-24

PROPORTION RELATIVE TO TOP LEVEL = 0.852994 2
0***SEPERATE 2 SUPER,SUBS 0 4 SPFAC 0.53649E 02
00-00
04-29 05-56 03-15
06-45 07-11

ORIGINAL PAGE IS
OF POOR QUALITY

>type classyn exec

CLASSYN EXEC FILE

&CONTROL OFF
CP SPOOL D CONT NOH TO BATCH
&PUNCH BATCH MACHINE BATJSC
&PUNCH BATCH ID JSC235 JSC235 TENT L
&PUNCH BATCH OUTPUT HOUSTON HOUSTON
&PUNCH EXEC\$\$
&PUNCH CP SPOOL 9 CLOSE
&PUNCH CP SPOOL 9 TO JSC235 START CL C NOHOLD
&PUNCH GETDISK JSC770 191 291 R B PASS AUCCOIN
&PUNCH GETDISK JSC235 191 391 W A PASS WRTE7
&PUNCH EXEC CFILE &1 &2 &3 &4 &5
&PUNCH RELEASE B (DET
&PUNCH CP Q T
&PUNCH CP SPOOL 9 CLOSE STOP
&PUNCH \$\$
CP SPOOL PUNCH NOCONT CLOSE
CP SPOOL PUNCH HOLD TO RSCS
&EXIT

ORIGINAL PAGE IS
OF POOR QUALITY

>type dot exec

DOT EXEC FILE

```
&CONTROL OFF
GETDISK /SC770 191 350 R B/A PASS AUCCIN
GETDISK TEMP 3M CLEAR DETACH
FIL 21 DISK DOT CC A (BLKSIZE 80 RECFM F LRECL 80 PERM
FIL 22 DISK FILE FT22F001 D (LRECL 800 BLKSIZE 800 XTENT 2100 PERM
FIL 3 TERMINAL (PERM
FIL 6 PRINTER ( PERM
FIL FT11F001 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F002 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F003 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F004 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F005 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F006 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F007 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F008 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F009 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F010 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F011 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F012 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F013 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F014 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F015 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F016 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F017 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F018 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F019 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F020 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F021 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F022 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F023 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F024 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F025 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F026 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT11F027 TAP1 (BLKSIZE 12356 RECFM U PERM
FIL FT12F001 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F002 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F003 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F004 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F005 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F006 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F007 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F008 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F009 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F010 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F011 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F012 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F013 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F014 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F015 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F016 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F017 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F018 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F019 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F020 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F021 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F022 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F023 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F024 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F025 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F026 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT12F027 TAP2 (BLKSIZE 12356 RECFM U PERM
FIL FT19F001 DISK &1 DOT2 A (LRECL 80 BLKSIZE 80 PERM
FIL FT19F002 DISK &1 DOT1 A (LRECL 80 BLKSIZE 80 PERM
LOAD MONITOR BLKCOM (CLEAR START NOMAP
```

>TYPE DOT CC A

SAMPLE DOT CONTROL CARD FILE

```
$DOTDATA
CHANNEL      DATA=1,2,3,4,5,6,7,8
DATAFILE     UNIT=11,FILE=7
DOTFIL       OUTPUT/UNIT=19,FILE=1
OPTION       LACIE
OPTION       PRINT
*END
DOT 2  N      1  6  7  8 10 11 13 14 19 21 25 29 33 35 37
DOT 2  N      39 40 41 42 44 45 47 49 50 51 53 54 55
DOT 2  N      56 57 59 61 65 67 73 78 83 84 86 87 88 91
DOT 2  N      92 94 95 99 101 105 109 111 113 121 122 123 125
DOT 2  N      128 129 130 131 132 135 139 141 145 147 149 153 154
DOT 2  N      155 156 159 160 161 162 163 165 166 167 168 169 170
DOT 2  N      171 175 177 179 183 185 189 191 192 193 194 195 196
DOT 2  N      197 203 204 207 208 209 20 22 28 32 34 36 38
DOT 2  N      60 62 64 68 72 100 104 136 140 142 146 152 172
DOT 2  N      174 176 180 182 186 190
DOT 2  S      2  3  4  5  9 12 15 16 17 18 23 27 31 43 46 48
DOT 2  S      52 63 69 71 75 77 79 80 81 82 85 89 90 93 97 103
DOT 2  S      107 115 116 117 118 119 120 124 126 127 133 137 143 151
DOT 2  S      157 158 164 173 181 187 198 199 200 201 202 205 206
DOT 2  S      26 30 58 66 70 76 96 102 106 134 148 150 178 188
$END*
$EXIT
```

SAMPLE DOT EXECUTION of Segment 1394

```
>def stor 2m
STORAGE = 02048K
R; T=0.01/0.02 10:33:06
```

>dot 1394

JSC770 191 HAS BEEN ATTACHED AS 350.
B (350) R/O

350 HAS BEEN LOGGED IN AS B/A DISK.

DASD 192 DETACHED

YOU ALREADY HAD A VIRTUAL DEVICE 192. IT IS BEING DETACHED.

TEMP 155 HAS BEEN ATTACHED AS 192. (003.00 MEGABYTES)

192 HAS BEEN LOGGED IN AS D DISK.

THE FOLLOWING NAMES ARE UNDEFINED:

WRTBM

EXECUTION BEGINS...

otype label exec

LABEL EXEC FILE

```
%CONTROL OFF
GETDISK JSC770 191 350 R B/A PASS AUCOIN
%BEEP = 1
-GET GETDISK TEMP 3M CLEAR DETACH
%IF %RETCODE EQ 0 %SKIP 7
%IF %BEEP LE 7 %SKIP 3
%TYPE NO 10 CYL TEMP DISK AVAILABLE
CP Q T
%EXIT
CP SLEEP 5 MIN
%BEEP = %BEEP + 1
%GOTO -GET
GETDISK LARSYS
Q DISK *
FILEDEF 3 TERM (PERM
FILEDEF 6 DISK LABEL6 LISTING D (PERM
FILEDEF 8 DISK %1 DOT1 A (LRECL 3060 RECFM U BLKSIZE 3060 PERM
FILEDEF FT11F001 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F002 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F003 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F004 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F005 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F006 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F007 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F008 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F009 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F010 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F011 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F012 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F013 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F014 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F015 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F016 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F017 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F018 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F019 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F020 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F021 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F022 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F023 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F024 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F025 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F026 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F027 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F028 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F029 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF FT11F030 TAP1 (BLKSIZE 3060 RECFM U DEN 1600 PERM
FILEDEF 12 DISK %1 UARM A (LRECL 80 BLKSIZE 80 PERM
FILEDEF FT19F001 DISK FILE FT19F001 A (LRECL 1860 BLKSIZE 1860 PERM
FILEDEF FT19F002 DISK FILE FT19F002 A (LRECL 1860 BLKSIZE 1860 PERM
FILEDEF FT20F001 DISK FILE FT20F001 A (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT20F002 DISK FILE FT20F002 A (LRECL 320 BLKSIZE 320 PERM
FILEDEF FT21F001 DISK LABEL CC A (LRECL 80 BLKSIZE 80 PERM
FILEDEF FT21F002 DISK FILE FT21F002 A (LRECL 80 BLKSIZE 80 PERM
FILEDEF FT22F001 DISK FILE FT22F001 A (LRECL 800 BLKSIZE 800 XTENT 2100 PERM
FIL FT23F001 DISK %1 5 A4 (LRECL 120 BLKSIZE 130 RECFM VS PERM
FIL 24 DISK FILE FT24F001 D4 (LRECL 1200 BLKSIZE 1250 RECFM VS PERM
FILEDEF 25 DISK FILE FT25F001 D (LRECL 132 BLKSIZE 132 PERM
FILEDEF 26 DISK FILE FT26F001 D (LRECL 132 BLKSIZE 132 PERM
FILEDEF 27 DISK FILE FT27F001 D (LRECL 132 BLKSIZE 132 PERM
FILEDEF 28 DISK FILE FT28F001 D (LRECL 132 BLKSIZE 132 PERM
FILEDEF 29 DISK FILE FT29F001 D (LRECL 132 BLKSIZE 132 PERM
FIL FT31F001 DISK FILE FT31F001 D (LRECL 3060 BLKSIZE 3060 RECFM U PERM
GLOBAL TXTLIB FORTRAN CHSLIB
LOAD IMAGE BLKCLA (CLEAR START NOMAP
LOAD MAXLABEL BLKCLA (CLEAR START NOMAP
CP REMOTE E TO HOUSTON
CP SPOOL PRINTER HOLD NOCONT
CP TAG QUE DEV E
L * * D (ALL
PRINT LABEL6 LISTING D
%IF %INDEX LT 2 %SKIP 8
%IF %2 EQ 1 %SKIP 2
%SP = %2 - 1
TAPE FSF %SP (TAP2
FIL INMOVE DISK FILE FT31F001 D (LRECL 3060 BLKSIZE 3060 RECFM U PERM
FIL OUTMOVE TAP2 ( BLKSIZE 3060 RECFM U DEN 1600 PERM
MOVEFILE
TAPE WTH 2 (TAP2
```

>TYPE LABEL CC A

SAMPLE LABEL CONTROL CARD FILE

CHANNELS 1,2,3,4,5,6,7,8
MAP PIXEL
DATA FILE = 8
SEGMENT 1394
PROC 07,02,80
END

\$END*

(1,1), (1,1), (196,1), (196,117), (1,117)

SAMPLE EXECUTION OF IMAGE AND LABEL FOR SEGMENT 1394

>label 1394

JSC770 191 HAS BEEN ATTACHED AS 350.

'350' REPLACES ' B (350) '

B (350) R/O

350 HAS BEEN LOGGED IN AS B/A DISK.

DASD 192 DETACHED

YOU ALREADY HAD A VIRTUAL DEVICE 192. IT IS BEING DETACHED.

TEMP 155 HAS BEEN ATTACHED AS 192. (003.00 MEGABYTES)

192 HAS BEEN LOGGED IN AS D DISK.

LARSLIB 29C HAS BEEN ATTACHED AS 19C.

Y (19C) R/O

19C HAS BEEN LOGGED IN AS Y DISK.

EXECUTION BEGINS...

IMAGE DATA EXTRACTED FROM TAPE, LAST LINE = 117

EXECUTION BEGINS...

3.1 HARDWARE DESCRIPTION

The CLASSY clustering program is operational on the IBM 3031. system at Purdue.

3.2 EXEC FILES

3.2.1 CLASSY EXEC FILES

CLASSY is called by using one of the following EXEC files:

CLASSY (segment number), (input tape number), (input file number), (output tape number), (output file number)
for interactive runs.

CLASSYN (segment number), (input tape number), (input file number), (output tape number), (output file number)
for batch runs.

Where segment number = name of control card file with type CC

input tape number = number of input tape

input file number = number of input file

output tape number = number of output tape

output file number = number of output file

These EXEC files assign (segment number) CC to be the control card input file which specifies the program options. The output files are (segment number) 1, ..., (segment number) (last iteration) and FT16F001.

3.2.2 DOT EXEC FILE

The pixel data files are extracted by executing the following EXEC file to call the DOT DATA processor.

DOT (segment number).

Where segment number = the name of the output files, (segment number) DOT1 and (segment number) DOT2. The name of the control card file is DOT CC.

***** Warning: The tape must be mounted and positioned prior to running the DOT EXEC.

3.2.3 IMAGE AND MAXLABEL EXEC FILE

The post-processor MAXLABEL and its associated program IMAGE are called by the following EXEC file:

LABEL (segment number)

where segment number is the number of the segment.

This EXEC file assigns LABEL CC to be the control card input file which specifies the program options. The report output is sent to the line printer and the labelled cluster map is placed on the D disk as FILE FT31F001.

***** Warning: The tape must be mounted prior to running the LABEL EXEC.

3.3 CONTROL CARDS

3.3.1 CLASSY CONTROL CARDS

The following control cards are input to the modified CLASSY program, and are analysed by SETUP9. In all cards the "keyword" begins in card column 1 and any parameters on the card are in card columns 11 through 72. Numbers in a series are separated by commas; blanks are optional.

1. "CHANNEL" CARD

EXAMPLE: CHANNEL 1, 5, 9, 13

The "CHANNEL" card specifies the channel numbers to be used in clustering the multi-channel data vectors. The maximum number of channels allowed is sixteen.

2. "NPTS" CARD

EXAMPLE: NPTS 2

This card specifies the number of pixels to skip between selected pixels.

3. "DATA" CARD

EXAMPLE: DATA FILE = 2

This card specifies the input file number. The default value is 1.

4. "MAP" CARD

EXAMPLE: MAP 1, 3, 5

This card specifies the iteration numbers for which intermediate pixel maps are to be drawn.

5. "LINES" CARD

EXAMPLE: LINES 1-10, 25-34

This card specifies the lines to be mapped on the intermediate pixel maps.

6. "SEGMENT" CARD

EXAMPLE: SEGMENT 1234

This optional card is used to specify the segment number used in the header of FILE FT31F001. The Accuracy Assessment system of programs requires this data in the header.

7. "PROCESS" CARD

EXAMPLE: PROCESS 2,11,80

This optional card is used to specify the date used in the header of FILE FT31F001. The Accuracy Assessment system of programs requires this data in the header.

8. "**END*" CARD

This mandatory card specifies the end of the control cards.

3.3.2 LABEL CONTROL CARDS

The following control cards are input to the post-processor MAXLABEL and its associated program IMAGE. The cards are analysed by the subroutine SETUPM. In all cards, the "keyword" begins in card column 1 and any parameters are entered from card columns 11 through 72. Numbers in a series are separated by commas; blanks are optional.

1. "CHANNEL" CARD

EXAMPLE: CHANNEL 1, 5, 9, 13

The "CHANNEL" card specifies the numbers of the channels to be used. The maximum number of channels allowed is sixteen.

2. "DATA" CARD

EXAMPLE: DATA FILE =2

This card is used to specify the input tape file number. The default value is 1.

3. "MAPOPT" CARD

EXAMPLES: MAPOPT PIXEL
 MAPOPT CLUSTER

This card is used to specify either a Pixel Map or a Cluster Map.

4. "SEGMENT" CARD

EXAMPLE: SEGMENT 1234

This optional card is used to specify the segment number used in the header of FILE FT31F001. The Accuracy Assessment system of programs requires this data in the header.

5. "PROCESS"

EXAMPLE: PROCESS 2,1,80

This optional card is used to specify the date used in the header of FILE FT31F001. The Accuracy Assessment system of programs requires this data in the header.

6. "**END*" CARD

This mandatory card specifies the end of the control cards.

3.3.3 FIELD DEFINITION CARDS FOR CLASSY AND MAXLABEL

1. "FLDNAM" CARD

The field definition cards(s) delineate the area on the image data tape to be used by CLASSY and MAXLABEL in terms of pixel coordinates (sample, line) for each vertex of the "field" up to a maximum of 10 vertices for a given field. An alphanumeric field identification may be supplied in card columns 1-6 but is not required. Coordinate pairs are in card column 11 through 72 and are enclosed in parentheses with the pairs separated by commas.

The first pair given for a field must be the incrementation desired in the lines and pixels to be read from the input image tape. I.E., "(2,3)" would indicate every second pixel on each line and every third line to be read.

The second and succeeding coordinate pairs are the (sample, line) coordinates of the vertices of the field. A continuation of coordinate pairs on the next card is indicated by an asterisk "*". Up to 10 coordinate pairs (vertices) are accepted for one field.

EXAMPLE: FLDNAM (2,3) , (2,1) , (196,3) , (100,50) *
(196,100) , (1,100) , (20,30)

The result of the above cards is that a rectangular area is read from the image data which bounds the given irregularly shaped field defined above. The coordinates of the rectangular area are (1,1) , (196,1) , (196,100) , (1,100).

The coordinates for the rectangular area are self-determined by the tape (file) reading program. Internally, the actual field coordinates which were input are used to extract only the pixels that are within the actual field defined.

The input field vertices must be defined on the card(s) in clockwise order.

2. "\$END*" CARD

This mandatory card specifies the end of the field definition cards.

3.4 SOFTWARE DESCRIPTION

3.4.1 CLASSY SUBROUTINES MODIFIED

3.4.1.1 Software Component No. 1 (CLINIT)

Linkage

CLINIT is called from CLASSY.

Interface

Interface is accomplished through a calling argument and the following common blocks:

/CLUS/, /MISC/, /STPAR/, /CLUSTER/, /INITL/ and /MXLL/.

Input

KROT - Index to root link.

Output

Common blocks initialized.

Storage Requirements

N/A

3.4.1.2 SOFTWARE COMPONENT NO. 2 (SETUP9)

Purpose

Read control cards for CLASSY.

Linkages

Interface is accomplished through common blocks /INFORM/, /CLUSTR/, /FILE/, /MAP/, /TIMERR/, and /WRTAP/.

Outputs

NOFSKP	/FILE/	Incremental number of files to skip
NOFEAT	/INFORM/	Number of channels
FETVEC	/INFORM/	Vertices array
NPTS	/CLUSTR/	Number of pixels to skip between pixels
NOCYCL	/CLUSTR/	Number of iterations
MAP	/MAP/	Array of iterations to map
MAPCT	/MAP/	Count of maps
LINES	/MAP/	Matrix of lines to map for each iteration
LINECT	/MAP/	Count of lines to map
TIMEMX	/TIMERR/	Maximum time
VARBL	/WRTAP/	Segment number and date

Storage Requirements

Not applicable.

Description

SETUP9 reads the control cards in CLASSY CC and saves the segment, date, tape and file numbers, map description, lines description, maximum time and number of iterations.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.1.3 SOFTWARE COMPONENT NO. 3 (STATIS)

Purpose

STATIS is the control subroutines for the computation and reporting part of CLASSY.

Linkages

STATIS is called by MULTI. STATIS calls DISC, CLASY2, CORECT, DOTSQ, VPV, VMTV, MPVS, ADJUST, CLDUMP and EXP.

Interface

Interface is accomplished through calling arguments and the following common blocks: /CLUS/, /MISC/, /STPAR/, /CLUSTER/, /RAND/, and /MXLL/.

Inputs

Temporary scrambled pixel file created by READTP.

Outputs

STATIS calls CLDUMP to output the data.

Storage Requirement

Not applicable

Description

STATIS was modified for the Maximum Likelihood Program to cause data to be calculated and saved at the end of each iteration through the complete data set. The subroutine additions (1) call CALRPR to calculate the relative proportions, and (2) set MXLL in common block /MXLL/ to 1 to cause CLPR to write a file record for each active cluster.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.1.4 SOFTWARE COMPONENT NO. 4 (CLPR)

Purpose

Report intermediate data to a print file; save data for post-processor MAXLABEL.

Linkages

CLPR is called from CLDUMP, ADJUST, SEPER and JOIN. CLPM calls LOCK, MORSTR, FREE, MORSTR and MINV.

Interface

Interface is accomplished through a calling sequence and the following common blocks /CLUS/, /MISC/, /STPAR/ and /MXLL/.

Inputs

KL - Index to LINK
IN - Not used
SUM - Data to be displayed
SKEW - Data to be displayed
KURT - Data to be displayed
RELP - Data to be saved on file
VOLRT - Data to be saved on file
DCON - Data to be saved on file
MEANS - Data to be saved on file
COVAR - Data to be saved on file

Outputs

Report on report file.

Storage Requirement

Not applicable.

Description

CLPR reports to all of the mathematical variables on a report file. The variables RELP, VOLRT and DCON and the MEANS array and COVAR matrix are saved on the file for the post-processor MAXLABEL.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.2 CLASSY SUBROUTINE ADDED

3.4.2.1 SOFTWARE COMPONENT NO. 1 (CALRPR)

Purpose

Calculate the relative probability of each pixel belonging to each class.

Linkages

CALRPR is called by STATIS CALRPR calls ISPLIT.

Interface

Interface is accomplished through the /CLUS/, /MISC/, /STPAR/ and /MXLL/ common blocks.

Inputs

KROTIN	Calling sequence	Index to root link
INDEX	/CLUST/	index to cluster data
LSUBS	/CLUST/	chain of sub-cluster
PROP	/CLUST/	
PRIRCM	/CLUST/	

Outputs

RELPRP /MXLL/ Relative proportions array

Storage Requirement

Not applicable.

Description

CALRPR determines the relative proportion for each link from the root link by dividing the PROP of the current link by the product of PRIRCM for the previous link and the relative proportion for the previous link.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.3 IMAGE PROCESSOR AND SUBROUTINES

3.4.3.1 SOFTWARE COMPONENT NO. 1 PROCESSOR (IMAGE)

Purpose

Create an input file for the MAXLABEL processor from a JSC Universal Image Tape.

Linkages

Interface is accomplished through common blocks /INFORM/ and /CLUSTER/.

Outputs

Pixel file for MAXLABEL Processor.

Storage Requirement

Not applicable.

Description

IMAGE calls SETUP9 to read the LABEL control cards to describe the pixel data needed for the MAXLABEL processor. The subroutine KREDTP calls the LARSYS subroutines to read the JSC Universal Image Tape and moves the pixel data to the pixel file for the MAXLABEL processor.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.3.2 SOFTWARE COMPONENT NO. 2 (SETUPM)

Purpose

Read control cards for IMAGE and MAXLABEL.

Linkages

Interface is accomplished through common blocks /INFORM/.
/CLUSTR/ and /WRTAP/.

Outputs

NOFSKP	/FILE/	Incremental number of files to skip
NOFEAT	/INFORM/	Number of channels
FETVEC	/INFORM/	Vertices array
NPTS	/CLUSTER/	Number of pixels to skip between pixels
VARBL	/WRTAP/	Segment number and date

Storage Requirements

Not applicable.

Description

SETUPM reads the control cards in LABEL CC and saves the segment, date, channel information and map option.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.3.3 SOFTWARE COMPONENT NO. 3 (KREDTP)

Purpose

Read lines of data from image tape.

Linkages

KREDTP is called the post-processor IMAGE. This subroutine calls TAPHDR, FLDINT, LINERD and FDLINT.

Interface

Interface is accomplished through common blocks /INFORM/, /CLUSTR/ and /FILE/.

Inputs

NOFSKP	/FILE/	Incremental number of files to skip
NPTS	/INFORM/	Number of pixels to skip between pixels
NOFEAT	/INFORM/	Number of channels
FETVEC	/INFORM/	Vertices array

Outputs

FILE of pixels as described by control cards.

Storage Requirement

Not applicable.

Description

KREDTP is calls TAPHDR to read the tape header, LAREAD to read the field and vertices information, FLDINT to position tape for this field, LINERD to read lines from the universal format tape.

Flowchart

Not applicable.

Listing

See Appendix A for program.

Error Message

FIELD DEFINATION INFORMATION EXCEEDS 2000 WORDS. END-OF-TAPE
REACHED BEFORE END OF FIELD.

Data Mesaages

Vertices listed.

3.4.4 MAXLABEL PROCESSOR AND SUBROUTINES

3.4.4.1 SOFTWARE COMPONENT NO. 1 (MAXLABEL)

Purpose

Maxlabel estimates the probability of observing a particular labelled class given that a particular cluster has been observed (BETA). These estimates are used to produce estimates of the proportion of each labelled class present in the scene. The proportion estimates are computed in two different ways: The first assumes that clusters are to be "bias corrected" using the BETA's. The second assumes that clusters are labelled using the BETA s.

Linkages

MAXLABEL calls SETUPM, ALLPXI, BAPLS, PRTBAP, PRTAP, PRTAP2 and WRTLNS.

Interface

Interface is accomplished through calling sequences, blank common and /FILE/ common blocks.

Inputs.

Control card file

LABEL CC

Image input file

CLASSY cluster statistical parameters. (segment number) 1, ...,
(segment number) (last iteration)

Outputs

Iteration Report (Estimated BETA's, cluster labels
 and proportions of each class present.)

Pixel Labelled Dot Map

Cluster Labelled Dot Map

Unlabelled Dot Map

Entropy and Posterior Probability for each Cluster Report

Pixel Labelled Cluster Map

Cluster Labelled Cluster Map

Unlabelled Cluster Map on Tape

Storage Requirement

Not applicable.

Description

MAXLABEL (1) reads the LABEL CC file to determine the segment number, processing date and data description (2) reads the dot data file and (3) reads the CLASSY cluster statistical parameters file. The iterative process then begins to calculate the estimates. The class and cluster labels are saved for maximum estimates.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.2 SOFTWARE COMPONENT NO. 2 (SETUPM)

See 3.4.3.2 for description of SETUPM.

3.4.4.3 SOFTWARE COMPONENT NO. 3 (READCC)

Purpose

Read CLASSY cluster statistic parameters into common block /CLASY/.

Linkage

READCC is called from MAXLABEL.

Interface

Interface is accomplished through blank common and /CLASY/ blocks.

Inputs

File from CLASSY. (Segment number) (Last iteration number).

Outputs

NOCC	/blank common/	Number of CLASSY clusters
RLPRP	/blank common/	Relative proportion array
CCLRT	/blank common/	Normalization factor elements
CDCON	/blank common/	Normalization factor elements

Storage Requirements

Not applicable.

Description

READCC reads the data from CLASSY describing the clusters.

Flowchart

Not applicable.

Listing

See Appendix B for program.

3.4.4.4 SOFTWARE COMPONENT NO. 4 (ALLPXI)

Purpose

Calculate the probability of X (dot data pixel) given I (Classy Cluster) for each X in the dot data file.

Linkages

ALLPXI is called by the main program MAXLABEL. ALLPRI calls DOTSQK and GETCC.

Interface

Interface is accomplished through blank common.

Inputs

NOCC	/blank common/	Number of CLASSY Cluster
ITOTDT	/blank common/	Total number of dots
MQ	/blank common/	Number of channels
IDOTS	/blank common/	Dot data pixels
CMEANS	/blank common/	CLASSY cluster mean matrix

Outputs

PXI	/blank common/	Probability of pixel belonging to CLASSY cluster.
-----	----------------	---

Storage Requirement

Not applicable.

Description

The array PXI is created by subtracting the CLASSY cluster mean value from the dot data pixel value for each channel. The product of this array and the covariance matrix for the CLASSY cluster is created. The probability is calculated as $P(X.I) = E(-PRODUCT/2.) * E(-DCON/2.) / CVOLRT$

Where DCON and CVOLRT are the normalization factor elements of the CLASSY cluster.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.5 SOFTWARE COMPONENT NO. 5 (BAPLS)

Purpose

Sum products in a class for all dot-cluster combinations.

Linkages

BAPLS is called by MAXLABEL.

Interface

Interface is accomplished through blank common.

Inputs

NOCC	/blank common/	Number of CLASSY cluster
NOCAT	/blank common/	Number of classes
ITOTDT	/blank common/	Total number of dots
IDOTS	/blank common/	Dot data pixels
BETA	/blank common/	Prior estiamte
RLPRP	/blank common/	Relative porportion for cluster
PX	/blank common/	Probability of pixel belonging to cluster

Outputs

SLK	/blank common/	Sum of products by class and cluster
SK	/blank common/	Sum of products by cluster

Storage Requirement

Not applicable.

Description

For each dot the following calculations are made:

- (1) The class of the dot is determined
- (2) The products of $BETA(\text{class, cluster}) * RLPRP(\text{cluster}) * PX(\text{cluster, dot})$ are summed.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.6 SOFTWARE COMPONENT NO. 6 (PRTELB)

Purpose

Construct and print estimate for each labelled class.

Linkages

PRTELB is called by the main program MAXLABEL.

Interface

Interface is accomplished through blank common.

Inputs

BETA /blank common/ Prior estimate

RLRP /blank common/ Relative proportion

Outputs

Report on report file.

Storage Requirement

Not applicable.

Description

PRTELB creates the sum of the products $BETA * RLPRP$ for each class-category combination.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.7 SOFTWARE COMPONENT NO. 7 (PRTBAP)

Purpose

Construct and print labeled cluster map for each class-cluster.

Linkages

PRTBAP is called by the main program MAXLABEL.

Interface

Interface is accomplished through the blank common and /MPPXL/ common blocks.

Inputs

ITOTDT	/blank common/	Total dots
IDOTS	/blank common/	Dot location
NOCAT	/blank common/	Number of categories
BETA	/blank common/	Prior estimate
RLPRP	/blank common/	Relative proportion
PX	/blank common/	Pixel value
LABELS	/blank common/	Category labels

Outputs

MPXLA /MPPXL/ Pixel labels.

Storage Requirement

Not applicable.

Description

The maximum product for each prior estimate * relative proportion * pixel value is determined. A matrix is constructed of the class labels corresponding to the maximum products. This matrix is printed.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.8 SOFTWARE COMPONENT NO. 8 (PRTAP)

Purpose

Construct and print labeled cluster map for each cluster.

Linkages

PRTAP is called by the main program MAXLABEL.

Interface

Interface is accomplished through blank common and /MPPXL/ common blocks.

Inputs

ITOTDT	/blank common/	Total number of dots
RLRPR	/blank common/	Relative proportion for class
PX	/blank common/	Pixel value for class
NOCC	/blank common/	Number of CLASSY cluster
LBLCST	/blank common/	Labels for CLASSY clusters

Outputs

MPXLA /MPPXL/ Class labels

Storage Requirement

Not applicable.

Description

The maximum product for each relative proportion * pixel value is determined. A matrix is constructed of the class labels corresponding to the maximum products. This matrix is printed. The entropy for each class-CLASSY cluster and the probability for each pixel-CLASSY cluster are calculated and printed.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.9 SOFTWARE COMPONENT NO. 9 (PRTAP2)

Purpose

Print labelled cluser map for each cluster.

Linkages

PRTAP2 is called by the main program MAXLABEL.

Interface

Interface is accomplished through blank common and /MXPPXL/ common blocks.

Inputs

ITOTDT	/blank common/	Total number of dots
NOCC	/blank common/	Number of CLASSY clusters
RLPRP	/blank common/	Relative proportion for CLASSY cluster
PX	/blank common/	Pixel value for CLASSY cluster
LBLCSS	/blank common/	Labels for CLASSY cluster categories

Outputs

Line written to report file of CLASSY cluster categories corresponding to pixel.

Storage Requirement

Not applicable.

Description

The maximum product for each relative proportion * pixel value is determined. A matrix is constructed of the cluster labels corresponding to the maximum products. This matrix is printed.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.10 SOFTWARE COMPONENT NO. 10 (WRTLNS)

Purpose

- (1) Read radiance values for lines of original pixel data,
- (2) Print heading for reports, and
- (3) Call subroutines to calculate report data.

Interface

WRTLNS is called by MAXLABEL. WRTLNS calls WRTHED, PXILN, LNBAP, WRTLN, LNAP, LNAP2 PAGE.

Inputs

Temporary file on unit 24.

Outputs

Pixel Labelled Cluster Map
Cluster Labelled Cluster Map
Unlabelled Cluster Map

Storage Requirement

Not applicable.

Description

WRTLNS reads a description of the lines from the temporary file. Report headings are written to files to be saved for each of the reports. The lines of radiance values are then read, the report calculations made and the report lines written to temporary report files. The temporary report files are then sent to the printer.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.11 SOFTWARE COMPONENT NO. 11 (LNBAP)

Purpose

Print labelled cluster map for each class-cluster,

Pixel cluster = Max (Beta * alpha * P(X.I)).

Linkages

Interface is accomplished through /PXLLN/, /MPPXL/ and blank common blocks.

Inputs

IBEGIN	/PXLLN/	First pixel on line
IEND	/PXLLN/	Last pixel on line
BETA	/blank common/	Prior estimate
RLPRP	/blank common/	Relative proportion
PXLN	/PXLLN/	Probability of pixel given cluster

Outputs

Report line written on labelled cluster map file.

Storage Requirement

Nct applicable.

Description

Each pixel in the line of data is processed for every category-cluster combination to determine the maximum sum of the class products for the category where the product = the estimate * the relative proportion * the probability that the pixel belongs to the cluster.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.12 SOFTWARE COMPONENT NO. 12 (PXILN)

Purpose

Calculate the probability of X (dot data pixel) given I (CLASSY cluster) for each X in the line in the image file.

Linkages

PXILN is called by WRTLNS. PXILN calls GETCC and DOTSQK.

Interface

Interface is accomplished through blank common and /PXLLN/.

Inputs

LNDOTS	/PXLLN/	
CMEANS	/blank common/	CLASSY mean array
MQ	/blank common/	Number of channels
CVRIN	/blank common/	CLASSY covariance matrix
DCON	/blank common/	Normalization factor element
CVOLRT	/blank common/	Normalization factor element

Outputs

PXLN /PXLLN/ Probability of X given cluster.

Storage Requirements

Not applicable.

Description

PXILN makes the pixel data calculations for each CLASSY cluster by calling GETCC to read the data for the cluster and then processing each dot data pixel using that cluster data to calculate the probability of that dot data pixel given that CLASSY cluster.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.13 SOFTWARE COMPONENT NO. 13 (GETCC)

Purpose

Move one set of CLASSY data from arrays to corresponding scalars.

Linkage

GETCC is called from GETCC.

Interface

Interface is accomplished through blank common and /CLASSY/ blocks.

Input

ICC /blank common/ current class

Output

RELPRP	/blank common/	Relative proportion
CVOLRT	/blank common/	Normalization factor element
CMEANS	/blank common/	CLASSY cluster mean array
CVRIN	/blank common/	Covariance matrix
DCON	/blank common/	Normalization factor element

Storage Requirement

Not applicable.

Description

GETCC moves data for this specified class from the arrays of CLASSY data.

Flowchart

Not applicable.

Listing

See Appendix A for program

3.4.4.14 SOFTWARE COMPONENT NO. 14 (DOTSQK)

Purpose

Calculate the inner product DIFXMN. DIFXMN relative to the metric CVRIN.

Linkages

DOTSQK is called from ALLPXI.

Interface

Interface is accomplished through calling arguments.

Inputs

MQ Number of channels
DIFXMN Array of differences between pixel values and CLASSY mean.
CVRIN CLASSY covariance matrix.

Outputs

DOTSQK enter product DIFXMN. DIFXMN relative to the metric CVRIN.

Storage Requirement

Not applicable.

Description

DOTSQK calculates the inner product DIFXMN. DIFXMN relative to the metric CVRIN.

Flowchart

Not applicable.

Listing

See Appendix A for program.

3.4.4.15 SOFTWARE COMPONENT NO. 15 (PAGE)

Purpose

Read data from temporary file and write report heading and column headings.

Linkages

PAGE is called by WRTLNS.

Interface

Interface is accomplished through a temporary file.

Inputs

IUNIT temporary file unit.

Outputs

Report heading written on report file.

Storage Requirement

Not applicable.

Description

PAGE reads the temporary file and writes the data on the report file.

Flowchart

Not applicable.

Listing

See Appendix A for program.

4. OPERATION

CLASSY, DOTDATA, IMAGE and LABEL are operational on the IBM 3031 computer at LARS, West Lafayette, Indiana.

The programs, EXEC files and CC files can be loaded from tape 3956, file 5.

CLASSY is executed by entering the following commands after signing on the computer system.

```
DEF STOR 2M
TAPMOUNT (Tape Number) TAP1 RO 1600
CLASSY or CLASSYN (Segment Number)
```

Control inputs is read from (Segment Number) CC.

Text output in on the terminal and line printer which are assigned in the EXEC, and the One Channel Unlabelled Tape File is on the output tape designated in the execute statement.

DOTDATA is executed by entering the following commands:

```
TAPE REW
DOT (Segment Number)
```

Control input is read from DOT CC.


Text output is on the terminal and line printer, and the Ground Truth Data File is on (Segment Number) DOT1 and (Segment Number) DOT2.


IMAGE and LABEL are executed by entering the following commands:

```
TAPE REW
LABEL (Segment Number)
```

Control input is read from LABEL CC.

Text output is on the terminal and line printer, and the One Channel Labelled Tape File is on the tape designated in the execute statement.





APPENDIX A
LISTINGS OF MODIFIED CLASSY SUBPROGRAMS
LISTINGS OF IMAGE AND MAXLABEL PROGRAMS

FILE: CLIPIT FOLIOAN A CONVERSATIONAL MONITOR SYSTEM

```

SUBROUTINE CLUST(R20T)
  THIS ROUTINE CONTAINS THE VARIOUS STATEMENTS NECESSARY TO
  INITIALIZE THE CLUSTERING ALGORITHM.
  REAL*8 XTEMP,VTEMP,ZTEMP,INCLC,INPCL
  DIMENSION INCLC(27),LSUMS(30),LSUPER(25),LOA(124),PSYMK(12),
  1 PCUM(26),PSCW(25),CTM(24),CTOT(23),LW(22),SPEAC(21),
  2 PCUM(20),CTOT(19),OBS(18),OBS(17),VOLIN(16),VOLRT(15),PCON(14),
  3 PCOR(13),NRES(12),BASS(12),PST(11),OCIN(10),PCOR(7),
  4 OPERIC(9),OPEIN(4)
  DIMENSION VTEMP(475),GEN(999),SPEFF(999),ALINK(11),
  1 EQUIVLENCE (LINK(11),ALINK(11)),(LINK(31),INDEX(27))
  EQUIVLENCE (LINK(31),LSUMS(30))
  EQUIVLENCE (LINK(31),LSUPER(25))
  1 LINK(31)=PSYMK(12)
  2 LINK(31)=CTM(24)
  3 LINK(31)=CTOT(23)
  4 LINK(31)=OBS(18)
  5 LINK(31)=OBS(17)
  6 LINK(31)=VOLIN(16)
  7 LINK(31)=VOLRT(15)
  8 LINK(31)=PCON(14)
  9 LINK(31)=PCOR(7)
  COMMON/CLUST/ JUNK(12),NAPL,NTOP,NTHSZ,NJANT,LINK(14000)
  DIMENSION IAXAP(31),LV(3),LV(3)
  EQUIVLENCE (LV(1),LV(1)),(LV(2),LV(2))
  1 (LV(3),LOVAR), (LV(1),LSUM), (LV(2),LSKE4), (LV(3),LSUM)
  COMMON /MISC/ MO,MN,ML,LV,NINCLC,MXAR,NTINI,AKOOT,EPS,DELT,
  1 AMQ,OCN,NOVFLD,XINFLD,XADJIN,ELIMTH,SPDTH,VFAC,AMH,SRLTH,
  2 INDIVL,WFACT,OPTSO,PATH,SMVTH,DIFAC,GFACTH,AMDFAC,
  3 AMQIN,AMQMAX,AMQAT,VOLLIM,ALIAS,PJOIN,VJOIN,WSIM,WDELIM,
  4 BETTER,MODE,CORLEN,SPCON
  COMMON /STPAR/ALIT,CONLV,SKCHI,TXND,TRCHI,URKWD,URKCHI,
  1 PACCEL(2),MACCEL(2),VACCEL(2)
  COMMON/CLUSTER/ BEGIN,TOTWDD,CLSNAM,IPT,JOLD,SYM(61)
  1 LOCAT,PRNT(4),KLOC,PRTHC,PROUT,TOTPIX,
  2 SCRAML,HUEPIX,HUFTOT,HUEFSD,VOLIMP,LUFD
  3, MAXHE, AREA, NPTS, NWPTS, NPTS, LHOF, IOL,NOCYCL
  INTEGER TOTWDD,SYM,PRNT,PRTHC,PROUT,TOTPIX,SCRAML,HUEPIX,HUFTOT
  1,CLSNAM
  COMMON /MXLL/ MXLLMT,MXLLFH,HFLPRP(200)
  COMMON /INIT/INTF,DEVINI,CHANIN
  CHIVAL (OF)=BFF(1,--P22/OF+CONLV*SORT(.222/OF))**3
  AMQ=MO
  DEFINE VALUE OF SEPTH IN TERMS OF CHI SQUARE VALUE
  SEPTH = (CHIVAL (DFT))/2
  WE FIRST SET UP VARIOUS INDEX ARRAYS FOR A PARTICULAR
  NUMBER OF CHANNELS MO.
  SET UP THE TRIANGULAR POSITION ARRAY MXAR.
  MW=0
  DO 10 I=1,31
  10 MXAR(I)=0
  MX=MAX(1,MW+1)
  MX=MAX(MW+1)
  IF SE=V
  20 WE SET UP THE ORIGIN VECTORS, LR AND LV, OF THE VARIOUS ARRAYS
  AND VECTORS IN A CLUSTER NODE.
  NINCLC=1
  DO 21 I=1,3
  21 NINCLC=NINCLC+MM
  DO 22 I=1,3
  22 LV(I)=NINCLC
  NSCAL=25
  NINCLC=NINCLC+NSCAL-1
  WE MUST ALSO SET UP SOME THRESHOLDS FOR USE BY THE STATISTICAL
  SYSTEM.
  SKCHI=(ALQ+2)*(AMQ+.4)*CHIVAL (AMQ)

```

FILE: C I N I T F O R T E A M A

FILE: SETUP0 FORTRAN A CONVERSATIONAL MONITOR SYSTEM

FILE: \$FTIPQ F01PTAN A

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: SFTUP9 FORTRAN A CONVERSATIONAL MONITOR SYSTEM

```

C      NPTS = NPTS - 1
C      GO TO 10
C      NPOS CARD, NUMBER OF POSM POSITIONS FROM WHICH TO OBTAIN DATA FOR
C      CLASSY3.50 THAT THE DATA WILL BE SCRAMBLED
C      150 J=NUMBER(CARD,COL,NPOS,K0)
C      GO TO 10
C      SYMBOL CARD
C      170 ICNT=ICNT+1
C      IF (ICNT.GT. 41) GO TO 10
C      180 N=NXTRCH(CARD,COL)
C      IF (M.FO. BLANK) GO TO 10
C      IF (M.FO. KOMA) GO TO 180
C      SYM(ICNT)=M
C      GO TO 170
C      PRINT OPTION CARD NO LONGER VALID
C      190 GO TO 10
C      DATA FILE CARD
C      260 M = NXTRCH(CARD,COL)
C      IF (M.FO. BLANK) GO TO 10
C      IF (M.FO. JRCO) GO TO 265
C      IF (M.FO. FRCO) GO TO 267
C      263 WRITE(6,750)
C      750 FORMAT(1, ERROR ON DATA FILE CARD)
C      265 J = FTRIDP(CARD,COL,EQUIVEC)
C      IF (J.FO. -1) GO TO 263
C      M = NUMBER(CARD,COL,DATAP,ZERO)
C      COL = COL - 1
C      GO TO 260
C      267 J = FTRIDP(CARD,COL,EQUIVEC)
C      IF (J.FO. -1) GO TO 263
C      M = NUMBER(CARD,COL,DATFIL,ZERO)
C      DATFIL = DATFIL - 1
C      IF (DATFIL.LT. 0) DATFIL = 0
C      COL = COL - 1
C      GO TO 260
C      ITERATION CARD
C      270 J = NXTRCH(CARD,COL)
C      IF (J.FO. BLANK) GO TO 10
C      COL = COL - 1
C      K = NUMBER(CARD,COL,TEMP,K0)
C      NOCYCL = TEMP(1)
C      GO TO 10
C      MAP CARD--MAY SPECIFY SERIES OF ITERATIONS TO BE MAPPED OR 'ALL'
C      300 EXAMPLES: 1,3,5,7,9
C      301 NO 301 I = 1,10
C      MAP(I) = 0
C      J = NXTRCH(CARD,COL)
C      IF (J.FO. BLANK) GO TO 10
C      IF 'ALL' WAS REQUESTED, GO READ NEXT CARD
C      IF (J.FO. KA) GO TO 10
C      SERIES OF NUMBERS REQUESTED
C      COL = 0
C      MAPCT = NUMBER(CARD,COL,MAP,K0)
C      GO TO 10
C      LINES CARD--LINES TO BE PRINTED. NUMBERS OR 'ALL' MAY BE SPECIFIED
C      350 EXAMPLES: 'ALL'
C      DO 351 I = 1,10
C      351 LINES(I,J) = 0
C      GET FIRST NONBLANK CHARACTER
C      J = NXTRCH(CARD,COL)
C      IF (J.FO. BLANK) GO TO 10
C      IF (J.FO. KA) GO TO 10
C

```


FILE: SFTUPO FORTPAN A CONVERSATIONAL MONITOR SYSTEM

```

C SERIES OF NUMBERS SPECIFIED
355 COL = COL - 1
C UP TO 10 NUMBERS OR SERIES MAY BE SPECIFIED
C MOVE SERIES OF NUMBERS TO ARRAY 'TEMP', STORE COUNT IN KOUNT
N = 1
KOUNT = NUMBER (CARD, COL, TEMP, K0)
N = 1
C NUMBER OR SERIES OF NUMBERS SEPARATED BY COMMAS
361 CONTINUE
DO 365 J = N, KOUNT
  LINES(NEXT, 1) = TEMP(J)
  LINES(NEXT, 2) = TEMP(J)
  NEXT = NEXT + 1
C SERIES COULD BE TERMINATED BY BLANK OR HYPHEN
COL = COL - 1
J = NATCHP (CARD, COL)
IF (J.FO. BLANK) GO TO 390
IF (J.FO. HYPHEN) GO TO 390
NEXT = NEXT + 1
KOUNT = NUMBER (CARD, COL, TEMP, K0)
LINES(NEXT, 2) = TEMP(1)
NEXT = NEXT + 1
IF (KOUNT.EQ. 1) GO TO 390
C SERIES OF FORM 1.25-28.51 GO TO PROCESS NEXT NUMBER AFTER HYPHEN
C BEGINNING OF NEXT GROUP OF LINES
N = 2
GO TO 361
390 LINECT = NEXT - 1
GO TO 10
C
C SET MAXIMUM TIME
400 J = NUMBER (CARD, COL, ITIME, 0)
TIMEPX = ITIME
GO TO 10
C
C *END* CARD
C 410 RETURN
C
C FORMATS
480 FORMAT (A4, 4X, 62A1)
490 FORMAT (I, 10A1D) INPUT CARD---IGNORED*/TS.A4, 4X, 62A1)
500 FORMAT (10X, 10A6)
510 FORMAT (10X, 2A6)
550 FORMAT (5X, A6, 4X, 62A1)
630 FORMAT (///, INPUT SUMMARY, ///)
      STOP
      END

```

SE102340
SE102340
SE102400
SE102410
SE102420
SE102430
SE102440
SE102450
SE102460
SE102470
SE102480
SE102490
SE102500
SE102510
SE102520
SE102530
SE102540
SE102550
SE102560
SE102570
SE102580
SE102590
SE102600
SE102610
SE102620
SE102630
SE102640
SE102650
SE102660
SE102670
SE102680
SE102690
SE102700
SE102710
SE102720
SE102730
SE102740
SE102750
SE102760
SE102770
SE102780
SE102790
SE102800
SE102810
SE102820
SE102830
SE102840
SE102850
SE102860
SE102870
SE102880

FILE: STATIS FORTRAN A CONVERSATIONAL MONITOR SYSTEMTM

A-8

FILE: STATUS FORTRAN A CONVERSATIONAL MONITOR SYSTEM

```

C INITIALIZE SWITCH FOR MAXIMUM LIKEHOOD
C KTHAD = 0
C HREF ABOVE GOFI IS THE SQUARE ROOT OF THE COVARIANCE
C WATERL, AND FFAC IS A POWER OF PI.
C KROT=KROTTIN
C NPISO = 0
C NIT = NOCYCL
C BMQ=.666666666667*AMQ
C KL = LSHS(KROT)
C KL=0
C ***** READ AND PROCESS DATA NIT TIMES *****
C ITER = 0
C 1 ITER = ITER + 1
C ***** READ 1 BUFFER OF SCRAMBLED DATA ***
C MQ = LENGTH OF ONE VECTOR
C RUFSIZ = RUFSIZ * MQ
C NHUFS = TOTWRD/RUFSIZ
C LBUF = MOD(TOTWRD, NHUFS)
C IF (LBUF .GT. 0) NHUFS = NHUFS + 1
C INADDR = 1ST WORD OF ORIG DATA ON FAST STORAGE
C INADDR = SCRAM
C RUFCNT = 0
C TOTWRD = 0
C MQ = LENGTH OF ONE VECTOR
C TOTPIX = TOTWRD/MQ
C 50 RUFCNT = RUFCNT + 1
C NHUFS = RUFSIZ
C IF (LBUF .GT. 0 .AND. RUFCNT .EQ. NHUFS) NHUFS = LBUF
C CALL RREAD (INADDR, PV, NHUFS, ISTAT)
C IF (ISTAT .GT. 0) GO TO 10
C INADDR = INADDR + NHUFS
C NPIXEL = NHUFS/MQ
C NDO = NPIXEL
C *** INSPECT EACH CLASS AND PROCESS EACH OF THE DATA POINTS ***
C DO 399 (DO=1, NDO)
C CHECK TIME EVE-Y 1000 POINTS
C IF (MOD((DO-1)*1000, NHUFS) .NE. 0) GO TO 100
C INITIM = 0
C FLPTIM = FLPTIM (INITIM)
C WRITE (6,9966) FLPTIM, OFGTIME, TIMEFX
C FORMAT (1, NF4.0, 16.5, 3F16.5)
C XX = (FLPTIM-OFGTIME) / 60000.
C WRITE (6,1111) XX, TIMEFX
C IF (XX .LT. TIMEFX) GO TO 100
C MAXIMUM TIME EXCEEDED, WRITE MESSAGES AND STOP
C WRITE (6,1111) XX, TIMEFX
C STOP
1111
100 CONTINUE
C ** THIS CODE GETS RANDOM NUMBERS. **
C GET NEXT POINT IN SEQUENCE
C WE USE MONTE-CARLO TECHNIQUES FOR LOW PROBABILITY CLASSES(P*PLIN)
C PCUM(KROT)=0.
C IF (INDEX(KL).NE. 0 .AND. KL.NE. 119)
C * WRITE (6,1000) 100 * INDEX(KL) * KL

```

CONVECTIONAL MONITOR SYSTEM

```

1000 FORMAT( 3X, '**** WARNING FROM STATIS **** ON THE ', 2X, 'IS,
C      * 2X, 'TIME, INDEX(KL)= ', 15, 3X, '0, KL= ', 15
C      PPRCM(KPOT)=0.
C      PDASS(KPOT)=1.
C      ISEC=0
C      KL=SPAS(KPOT)
C      KFAIR=KOT
C      GO DOWN CLUSTER TREE
C      170 IF(LEUS(KL).EQ.0) GO TO 131
C      C FIND MOTION MODE
C      PRIM(KL)=0.
C      PPRCM(KL)=0.
C      KFAIR=KL
C      KL=SPAS(KL)
C      GO TO 170
C      CHANGE***
C      CALC UNWEIGHTED NORMALIZED VECTOR REL
C      *USE = CURRENT *WEIGHT
C      131 IF(INDEX(KL).NE.0) GO TO 133
C      C
C      C USE NEW WEIGHTS AND MEANS IF ADJUST HAS BEEN CALLED
C      CALL CORRECT(REL,PV(1,100),OM(KL),OSUM(KL+1))
C      *USE=OM(KL)
C      CALL CORRECT(REL,PV(1,100),WK(KL),SUM(KL+1))
C      *USE=WK(KL)
C      PPRCM(KL)=CTM(KL)/(WKFAIR)-CTOT(KL)
C      GO TO 134
C      CHANGE***
C      133 CALL CORRECT(PFL,PV(1,100),OM(KL),OSUM(KL+1))
C      *USE=OM(KL)
C      134 OTSS(KL)=OTSS(OM(KL),WKIN(KL+1))**USE
C      OTSS(KL)=OTSS(KL)/4PCOM
C      IF(OTSS(KL).LT. 100.) GO TO 531
C      PCOM(KL)=0.
C      GO TO 134
C      531 CONTINUE
C      Y = -.5**OTSS
C      XTEMP = EXP(Y)
C      PCOM(KL)=XTEMP/VOLPT(KL)
C      138 IF(LEUS(KL).NE.0) PCOM(KL)=PCUM(KL)/PRIRC(KL)
C      SPUS=SPFAC(KL)/4PCOM
C      IF(SPUS.GT.XHFL0) GO TO 231
C      PST(KL)=POOP(KL)*PCOM(KL)
C      GO TO 134
C      C
C      C SET KL = LAST MODE IN STRING
C      231 IF(SPUS.LT.XHFL0) GO TO 232
C      PST(KL)=POOP(KL)*PCUM(KL)
C      GO TO 234
C      232 CONTINUE
C      77=EXP(SPUS)
C      PST(KL)=POOP(KL)*(PCOM(KL)+77*PCUM(KL))/(1.+77)
C      239 PCUM(KFAIR)=PCUM(KFAIR)+PST(KL)
C      PPRCM(KFAIR)=PPRCM(KFAIR)+POOP(KL)
C      179 KL=LINK(KL)
C      IF(KL)130,140,130
C      C GO UP TREE
C      149 KL=KFAIR
C      KFAIR=SUBP(KL)
C      IF(KFAIR.EQ.0) GO TO 131
C      C WE NOW HAVE THE RELEVANT CLASSES AND THEIR PROBABILITIES AVAILABLE.
C      C NEXT *F MAKE THE APPROPRIATE INDIVIDUAL FIRST-ORDER STATISTICS ADJ.
C      150 CONTINUE
C      PCUM(KPOT)=PCUM(KPOT)/PRIRC(KPOT)
C      IF(PCUM(KPOT).NE.0.) GO TO 141
C      CHANGE***
C      555 FORT( 6,555) IDG(KPOT)=PV(KPOT,100)*KPP=1.00
C      1 F10,2/5X, *VECTOT*,(5E12,0)
C      *IF( 3,5555) IDG(KPOT)=PV(KPOT,100)*KPP=1.00
C      5555 FORT( 1,55555) SUSPECTED BAD DATA POINT--STATIS**100=,15,*ROOT**
C      1 F10,2/ *VECTOT*,(4E8,3/7X,4E6,3)
C      C
C      KTHAD = KTHAD * 1
C      IF (KTHAD .LT. 50) GO TO 394
C      C
C      C SHORT JOB TOO MANY BAD POINTS

```

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: STATIS FORTRAN A CONVERSATIONAL MONITOR SYSTEM

```

1500 WRITE (6,1500)
      FORMAT (' JOB AHOOTED, TOO MANY RAD POINTS.')
      STOP
C 151 CONTINUE
      KLE=SQRT(KROT)
      KFAH=KDOT
      K(KROT)=K(KDOT)+PPASS(KROT)
      NPISO=NPISO+1
      KADJEC
C 153 CONTINUE
      IF (PST(KL).EQ.0.) GO TO 299
      PPASS=PPASS(KFAH)
      P=PST(KL)/(PCUM(KFAH)*PRIRCM(KFAH))*PPASS
      KLO=KL
      IF (P.GE.1) GO TO 140
      IF (DISC(MONTE).NE.1) GO TO 299
      PPASS=PPASS(KFAH)
      DEPR=MONTE
      GO TO 132
CHANGE***
140 IF (INDEX(KL).LE.0) GO TO 143
      CALL CUMECT(DEL,PV(1:100),*(KL),SUM(KL*1))
      GO TO 144
CHANGE***
143 CALL CUMECT(DEL,PV(1:100),OW(KL),OSUM(KL*1))
      GO TO 144
144 IF (P.GT.1.0) P=1.0
      PRINT 672,INDEX(KL),KL,INDEX(KFAH),
      1 KFAH,100.,P,PST(KL),PCUM(KFAH),PRIRCM(KFAH),PPASS,
      2 PRIR(KL)
      IF (P.GT.1.0) P=0.1
      IF (P.GT.1.0) P=0.1
      ALPHA=PRIR(KL)
      ALPHA=PRIR(KL)
      IF (OW(KL).EQ.0) GO TO 611
      Z0=(PCUM(KL)-PCUM(KL))/(PCUM(KL)+PCUM(KL)+1.E-37)
      Z0=Z0*Z0
      W0=PCUM(KL)+PCUM(KL)+Z0
      SOFAC(KL)=SOFAC(KL)+Z0*(2.+.95/(1.5-.9*Z0))
      CONTINUE
      IF (INDEX(KL).LT.0) GO TO 149
      VOLIN(KL)=VOLIN(KL)*(1.+ALOW*DISS(KL))
      VOLIN(KL)=VOLIN(KL)+VOLIN(KL)/VOLIN(KL)
      HERE WE KEEP VOLIN NEAR SORT(VOLIN) BY NEWTON'S METHOD.
      ZFAC=Z0/(1.+ALOW*.5)
      DCOM(KL)=DCOM(KL)+ZFAC*(3.+ZFAC*ZFAC)
      THE ABOVE CALCULATION TO THE LOG IS CORRECTED FOR IN ADJUST
      DEPR=DEPR(KL)+ZFAC*PRIRCM(KFAH)
      IF (P.GT.1.0) GO TO 142
      IF (P.GE.1) PPASS=PPASS(KL)
      CTOT(PT)=CTOT(KL)+P*PRIRPL
      GO TO 141
192 CTN(KL)=CTN(KL)+1.
      GO TO 141
190 CTOT(KL)=CTOT(KL)+(PPASSK-P)/(1.-PRIRPL)
      CTN(KL)=CTN(KL)+(P-PPASSK*PRIRPL)/(1.-PRIRPL)
      CONTINUE
CHANGE***
      CALL VBV(SUM(KL*1),P,PV(1:100))
      IF (INDEX(KL).LE.0) GO TO 143
      CALL VMTV(COVEC,V-IN(KL*1),*PL)
      CALL VMTV(COVEC,V-IN(KL*1),*PL)
      CALL VMTV(COVEC,V-IN(KL*1),*PL)
      CALL VMTV(COVEC,V-IN(KL*1),*PL)
      GO TO 144
143 CALL VMTV(COVAR,KL*1)+ALPHA*DEL
      CONTINUE
DISS(KL) CONTAINS THE GAUSSIAN DISTANCE OF THE POINT FROM THE CLUSTER
VMTN IS THE INVERSE COVARIANCE MATRIX (*** OVER W(KL)
      (THIS INTRODUCES SEVERAL SCALE FACTORS)
      COVEC IS THE CONTRAVARIANT FORM OF THE RELATIVE DISTANCE DEL.
      COVAR=VMTN*DEL
      WE NOW HAVE ALL THE LINEAR AND QUADRATIC STATISTICS AND PROCEED
      TO CALCULATE THE APPROXIMATED 3RD AND 4TH MOMENTS FOR TESTING.
      THESE MOMENTS ARE NOT CALCULATED EXACTLY: THE SQUARED
      DISTANCE OF A POINT FROM THE MEAN ACTUALLY SHOULD

```


FILE: CLPD FORTRAN & CONVERSATIONAL MONITOR SYSTEM

[illegible]


```

FILE: CLPP      FORTPAN  A      COINTEGRATIONAL MONITOR SYSTEM

163  FORMAT(/,.,, OLD MEAN*,6X*,5F13.6/(12*(5F13.6))
      CALL SQRV (ALINK(LA),G*F (LOWAP*,KL*1))
      DO 156 I=1,M0
156  ALINK(LA+I-1)=ALINK(LA+I-1)/OWUSE
      PRINT 166, (ALINK(LA+J-1),J=1,M0)
166  FORMAT(0,.,, OLD COVARIANCE*,5F13.6/(16X*,5F13.6))
      DO 157 I=2,M0
157  PRINT 165, I, (ALINK(LA+M0*I+J-M0-1),J=1,M0)
200  CALL FREE (LA,M0S)
      CALL FREE (L9,M0S)
      PRINT 109
109  FORMAT(/
      RETURN
      END

```

```

CLP01590
CLP01600
CLP01610
CLP01620
CLP01630
CLP01640
CLP01650
CLP01660
CLP01670
CLP01680
CLP01690
CLP01700
CLP01710
CLP01720

```

CAI

ILITIES OF THE CLUSTERS

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: CALPP FORTMAN A CONVERSATIONAL MONITOR SYSTEM

C 9992 WAIT (3.0002) (HELP(1), I=1.7)
FORMAT (1 LEAVING CALPP, REL PHOP = 0.76.2)
RETURN
END

CAL00000
CAL00010
CAL00020
CAL00030
CAL00040

```

C      IMPLICIT INTEGER (A-Z)
C      DIMENSION FLDINF(6), IDATA(1), FL(12)
C      DIMENSION IPUFF(104)

COMMON /INFO00/HEAD(42), MACTAP,
1  PAGES17, TAPCHK,
2  DIPSYM, TAPSYM,
3  SERIAL, TAPFSV,
4  MAXCLS, NOCL52,
5  TOTFID, NOFEAT,
6  VARS72, VARS74,
7  NOGAP, DIVS17,
8  XHIGH, XLOW
9  BLOCK(30), FEETVEC(30), HISVEC(30), INVEFT(30), HESTVC(30)
COMMON /CLUST0/ IHEGIM, TOTW20, CLSNAM, IPT, NOFLD, SYM(61),
1  LNCAT, PONT(4), KL4C, PRTEF, PROUT, TOTPIX,
2  SCRAM1, BUFP1X, BUFTOT, BUFS50, BUFP1, BUFT,
3  MAXHF, AREA, NIDS, NIDRS, NPTS, LBUF, IOL, NOCYCL

INTEGER TOTW20, SYM, PONT, PRTEF, PROUT, TOTPIX, SCRAM1, BUFP1X, BUFTOT
1  CLSNAM

EQUIVALENCE (FLDINF(1), LINEST), (FLDINF(4), SAMSTP),
* (FLDINF(2), LINEID), (FLDINF(5), SAMEND),
* (FLDINF(3), LINEIN), (FLDINF(6), SAMINC)

DIMENSION ARRAY(16000)

RESERVE 2000 LOCATIONS OF ARRAY FOR FIELD DEFINITION INFORMATION.
THE REMAINDER OF ARRAY IS USED FOR I/O BUFFERS.

FIELD INFORMATION STORED AS FOLLOWS
ARRAY(1) = FIRST FIELD NAME FOR THIS CLASS (NV)
(2) = END OF VERTICES FOR THIS FIELD (NV)
(3) = (3+NV*2) = ACTUAL VERTX NUMBERS
(4+NV*2) = TOTAL PIXELS IN THIS FIELD
(4+NV*2) - (10+NV*2) = FLDINF BLOCK FOR THIS FIELD

CALL SETUPM
CALL KODETO
STOP
END
SUBROUTINE KPEDIT
C      IMPLICIT INTEGER (A-Z)
C      PURPOSE: MOVE DATA FROM A UNIVERSAL FORMAT TAPE TO A TEMP DISK FILE
C      FROM THE IMAGE TAPE
C      DIMENSION FLDINF(6) = FL(12)
C      DIMENSION IPUFF(3200), IDATA(4200)

COMMON /INFO00/HEAD(42), MACTAP,
1  PAGES17, TAPCHK,
2  DIPSYM, TAPSYM,
3  SERIAL, TAPFSV,
4  MAXCLS, NOCL52,
5  TOTFID, NOFEAT,
6  VARS72, VARS74,
7  NOGAP, DIVS17,
8  XHIGH, XLOW
9  BLOCK(30), FEETVEC(30), HISVEC(30), INVEFT(30), HESTVC(30)
COMMON /CLUST0/ IHEGIM, TOTW20, CLSNAM, IPT, NOFLD, SYM(61),
1  LNCAT, PONT(4), KL4C, PRTEF, PROUT, TOTPIX,
2  SCRAM1, BUFP1X, BUFTOT, BUFS50, BUFP1, BUFT,
3  MAXHF, AREA, NIDS, NIDRS, NPTS, LBUF, IOL, NOCYCL

INTEGER TOTW20, SYM, PONT, PRTEF, PROUT, TOTPIX, SCRAM1, BUFP1X, BUFTOT
1  CLSNAM

```

```

C
C      COMMON /FILE/ NOFSKP
C      EQUIVALENCE (FLOINF(1),LINSTR), (FLOINF(4),SAMSTR),
*      (FLOINF(2),LIREND), (FLOINF(5),SAREND),
*      (FLOINF(3),LININC), (FLOINF(6),SAMINC)
C
C      DIMENSION ARRAY(14000)
C
C      RESERVE 2000 LOCATIONS OF ARRAY: FOR FIELD DEFINITION INFORMATION.
C      THE REMAINDER OF ARRAY IS USED FOR I/O BUFFERS.
C
C      FIELD INFORMATION STORED AS FOLLOWS
C      ARRAY(1) = FIRST FIELD NAME FOR THIS CLASS
C      (2) = NO. OF VERTICES FOR THIS FIELD (NV)
C      (3) - (3+NV*2) = ACTUAL VERTEX NUMBERS
C      (3+NV*2) = TOTAL PIXELS IN THIS FIELD
C      (4+NV*2) - (10+NV*2) = FLOINF BLOCK FOR THIS FIELD
C
C      DEFINE INPUT FILE TO BE UNIT 11
C      DEFINE FILE 22(2100,2000,10)
C      DATAP = 11
C      CALL TAPROP(DATAP,NOFSKP)
C
C      NOFLD=0
C      IPT=1
C
C* READ (1) FIELD NAME, (2) FIELD VERTICES, (3) FIELD INFORMATION
C      (4) NUMBER VERTICES, AND RETURN (5) NUMBER OF CARDS READ
C      ICK = LASTLOC(ARRAY(IPT),ARRAY(IPT+2),FLOINF,ARRAY(IPT+1),NOCRDS)
C      ICK=ARRAY(IPT+1)
C      NOFLD=NOFLD+1
C      NSAMP=(SAREND-SAMSTR)/SAMINC+1
C      FLOSAMEN
C      IREPT=2
C      IREPT=NOFLD-1
C      IREPT=NOFLD-1
C      WRITE (6,1000) NOFLD,ARRAY(IPT),NV,SAMINC,LININC,
*      (ARRAY(1),IREPT,IE)
C
C* POSITION TAP FOR THIS FIELD
C      CALL FLOINF(FLOINF,FETVEC,NOFEAT)
C      KNT=0
C
C      READ LINES OF DATA FROM UNIVERSAL FORMAT TAPE AND MOVE TO DISK
C      DO 70 LINE=LINSTR,LINEND,LININC
C      LINE=LINSTR
C
C      READ LINE FROM UNIVERSAL FORMAT TAPE (ENDTAP = -1 IF LAST LINE)
C      CALL LINEOD(DATAP,ENDTAP)
C      IF (ENDTAP.EQ.-1) GO TO 800
C
C      FIND SAMPLE INTERSECTS FOR THIS LINE - N1=NO. OF INTERSECTS
C      CALL FINT(ARRAY(IPT+2),NV,FL,LINE,SAMPS,N1)
C
C      WRITE DUMMY FIRST RECORD
C      NOLINES = (LINEND - LINSTR) / LININC + 1
C
C      STORE DATA ON THIS LINE INTO OUTPUT BUFFER
C      DO 60 I=1,2
C      I1=(FL(I)-SAMSTR)/SAMINC + 1
C      I2=(FL(I+1)-SAMSTR)/SAMINC + 1
C      IF (MOD(SAMSTR,SAMINC).NE. MOD(FL(I),SAMINC)) I2=I1+1
C      IF (I1.GT. IE) GO TO 60
C
C      I120 = 0
C      DO 50 J=I1,IF
C      KNT=KNT+1
C      DO 50 K=1,NOFEAT
C      I120=I120+1
C      ITEMP = (K-1)*NSAMP + J
C      ITHUFF(I,120) = ITEMP
C
C      50 CONTINUE
C
C      WRITE LINE ON TEMP DISK FILE
C      WRITE (24) I120, LINE=0, IR, IE, (IRUFF(I),I=1,I120)
C
C924    FORMAT (15,40I3)

```


FILE: IMAGE FORTAN A COMPENSATIONAL MONITOR SYSTEM

```

DTMFUNCTION EDIVEC(2)
DATA KKA/AA//KHPH/1-0//
DATA HRC/00//FACU//F//EDIVEC/1.00//
VACHL(10) = 242
ICMTER = 0
KA = KKA
ZERO = 0
C ASSUME VAL FOR MAP AND LINES CARDS
  ITHCT = 1
  MAPCT = 1
  LINES(1,1) = KA
  MAP(1) = KA
  DO 5 I=1,61
    5 SYM(I)=SYMS(I)
    NOFEAT=0
    WRITE(6,600)
    600 FORMAT(141, ' EXTRACT IMAGE DATA FROM UNIVERSAL FORMAT TAPE')
    WRITE(6,610)
    610 PUT THE NEXT CARD IN THE DFEAD BUFFER
    620
    630
    640
    650
    660
    670
    680
    690
    700
    710
    720
    730
    740
    750
    760
    770
    780
    790
    800
    810
    820
    830
    840
    850
    860
    870
    880
    890
    900
    910
    920
    930
    940
    950
    960
    970
    980
    990
    1000
    1010
    1020
    1030
    1040
    1050
    1060
    1070
    1080
    1090
    1100
    1110
    1120
    1130
    1140
    1150
    1160
    1170
    1180
    1190
    1200
    1210
    1220
    1230
    1240
    1250
    1260
    1270
    1280
    1290
    1300
    1310
    1320
    1330
    1340
    1350
    1360
    1370
    1380
    1390
    1400
    1410
    1420
    1430
    1440
    1450
    1460
    1470
    1480
    1490
    1500
    1510
    1520
    1530
    1540
    1550
    1560
    1570
    1580
    1590
    1600
    1610
    1620
    1630
    1640
    1650
    1660
    1670
    1680
    1690
    1700
    1710
    1720
    1730
    1740
    1750
    1760
    1770
    1780
    1790
    1800
    1810
    1820
    1830
    1840
    1850
    1860
    1870
    1880
    1890
    1900
    1910
    1920
    1930
    1940
    1950
    1960
    1970
    1980
    1990
    2000
    2010
    2020
    2030
    2040
    2050
    2060
    2070
    2080
    2090
    2100
    2110
    2120
    2130
    2140
    2150
    2160
    2170
    2180
    2190
    2200
    2210
    2220
    2230
    2240
    2250
    2260
    2270
    2280
    2290
    2300
    2310
    2320
    2330
    2340
    2350
    2360
    2370
    2380
    2390
    2400
    2410
    2420
    2430
    2440
    2450
    2460
    2470
    2480
    2490
    2500
    2510
    2520
    2530
    2540
    2550
    2560
    2570
    2580
    2590
    2600
    2610
    2620
    2630
    2640
    2650
    2660
    2670
    2680
    2690
    2700
    2710
    2720
    2730
    2740
    2750
    2760
    2770
    2780
    2790
    2800
    2810
    2820
    2830
    2840
    2850
    2860
    2870
    2880
    2890
    2900
    2910
    2920
    2930
    2940
    2950
    2960
    2970
    2980
    2990
    3000
    3010
    3020
    3030
    3040
    3050
    3060
    3070
    3080
    3090
    3100
    3110
    3120
    3130
    3140
    3150
    3160
    3170
    3180
    3190
    3200
    3210
    3220
    3230
    3240
    3250
    3260
    3270
    3280
    3290
    3300
    3310
    3320
    3330
    3340
    3350
    3360
    3370
    3380
    3390
    3400
    3410
    3420
    3430
    3440
    3450
    3460
    3470
    3480
    3490
    3500
    3510
    3520
    3530
    3540
    3550
    3560
    3570
    3580
    3590
    3600
    3610
    3620
    3630
    3640
    3650
    3660
    3670
    3680
    3690
    3700
    3710
    3720
    3730
    3740
    3750
    3760
    3770
    3780
    3790
    3800
    3810
    3820
    3830
    3840
    3850
    3860
    3870
    3880
    3890
    3900
    3910
    3920
    3930
    3940
    3950
    3960
    3970
    3980
    3990
    4000
    4010
    4020
    4030
    4040
    4050
    4060
    4070
    4080
    4090
    4100
    4110
    4120
    4130
    4140
    4150
    4160
    4170
    4180
    4190
    4200
    4210
    4220
    4230
    4240
    4250
    4260
    4270
    4280
    4290
    4300
    4310
    4320
    4330
    4340
    4350
    4360
    4370
    4380
    4390
    4400
    4410
    4420
    4430
    4440
    4450
    4460
    4470
    4480
    4490
    4500
    4510
    4520
    4530
    4540
    4550
    4560
    4570
    4580
    4590
    4600
    4610
    4620
    4630
    4640
    4650
    4660
    4670
    4680
    4690
    4700
    4710
    4720
    4730
    4740
    4750
    4760
    4770
    4780
    4790
    4800
    4810
    4820
    4830
    4840
    4850
    4860
    4870
    4880
    4890
    4900
    4910
    4920
    4930
    4940
    4950
    4960
    4970
    4980
    4990
    5000
    5010
    5020
    5030
    5040
    5050
    5060
    5070
    5080
    5090
    5100
    5110
    5120
    5130
    5140
    5150
    5160
    5170
    5180
    5190
    5200
    5210
    5220
    5230
    5240
    5250
    5260
    5270
    5280
    5290
    5300
    5310
    5320
    5330
    5340
    5350
    5360
    5370
    5380
    5390
    5400
    5410
    5420
    5430
    5440
    5450
    5460
    5470
    5480
    5490
    5500
    5510
    5520
    5530
    5540
    5550
    5560
    5570
    5580
    5590
    5600
    5610
    5620
    5630
    5640
    5650
    5660
    5670
    5680
    5690
    5700
    5710
    5720
    5730
    5740
    5750
    5760
    5770
    5780
    5790
    5800
    5810
    5820
    5830
    5840
    5850
    5860
    5870
    5880
    5890
    5900
    5910
    5920
    5930
    5940
    5950
    5960
    5970
    5980
    5990
    6000
    6010
    6020
    6030
    6040
    6050
    6060
    6070
    6080
    6090
    6100
    6110
    6120
    6130
    6140
    6150
    6160
    6170
    6180
    6190
    6200
    6210
    6220
    6230
    6240
    6250
    6260
    6270
    6280
    6290
    6300
    6310
    6320
    6330
    6340
    6350
    6360
    6370
    6380
    6390
    6400
    6410
    6420
    6430
    6440
    6450
    6460
    6470
    6480
    6490
    6500
    6510
    6520
    6530
    6540
    6550
    6560
    6570
    6580
    6590
    6600
    6610
    6620
    6630
    6640
    6650
    6660
    6670
    6680
    6690
    6700
    6710
    6720
    6730
    6740
    6750
    6760
    6770
    6780
    6790
    6800
    6810
    6820
    6830
    6840
    6850
    6860
    6870
    6880
    6890
    6900
    6910
    6920
    6930
    6940
    6950
    6960
    6970
    6980
    6990
    7000
    7010
    7020
    7030
    7040
    7050
    7060
    7070
    7080
    7090
    7100
    7110
    7120
    7130
    7140
    7150
    7160
    7170
    7180
    7190
    7200
    7210
    7220
    7230
    7240
    7250
    7260
    7270
    7280
    7290
    7300
    7310
    7320
    7330
    7340
    7350
    7360
    7370
    7380
    7390
    7400
    7410
    7420
    7430
    7440
    7450
    7460
    7470
    7480
    7490
    7500
    7510
    7520
    7530
    7540
    7550
    7560
    7570
    7580
    7590
    7600
    7610
    7620
    7630
    7640
    7650
    7660
    7670
    7680
    7690
    7700
    7710
    7720
    7730
    7740
    7750
    7760
    7770
    7780
    7790
    7800
    7810
    7820
    7830
    7840
    7850
    7860
    7870
    7880
    7890
    7900
    7910
    7920
    7930
    7940
    7950
    7960
    7970
    7980
    7990
    8000
    8010
    8020
    8030
    8040
    8050
    8060
    8070
    8080
    8090
    8100
    8110
    8120
    8130
    8140
    8150
    8160
    8170
    8180
    8190
    8200
    8210
    8220
    8230
    8240
    8250
    8260
    8270
    8280
    8290
    8300
    8310
    8320
    8330
    8340
    8350
    8360
    8370
    8380
    8390
    8400
    8410
    8420
    8430
    8440
    8450
    8460
    8470
    8480
    8490
    8500
    8510
    8520
    8530
    8540
    8550
    8560
    8570
    8580
    8590
    8600
    8610
    8620
    8630
    8640
    8650
    8660
    8670
    8680
    8690
    8700
    8710
    8720
    8730
    8740
    8750
    8760
    8770
    8780
    8790
    8800
    8810
    8820
    8830
    8840
    8850
    8860
    8870
    8880
    8890
    8900
    8910
    8920
    8930
    8940
    8950
    8960
    8970
    8980
    8990
    9000
    9010
    9020
    9030
    9040
    9050
    9060
    9070
    9080
    9090
    9100
    9110
    9120
    9130
    9140
    9150
    9160
    9170
    9180
    9190
    9200
    9210
    9220
    9230
    9240
    9250
    9260
    9270
    9280
    9290
    9300
    9310
    9320
    9330
    9340
    9350
    9360
    9370
    9380
    9390
    9400
    9410
    9420
    9430
    9440
    9450
    9460
    9470
    9480
    9490
    9500
    9510
    9520
    9530
    9540
    9550
    9560
    9570
    9580
    9590
    9600
    9610
    9620
    9630
    9640
    9650
    9660
    9670
    9680
    9690
    9700
    9710
    9720
    9730
    9740
    9750
    9760
    9770
    9780
    9790
    9800
    9810
    9820
    9830
    9840
    9850
    9860
    9870
    9880
    9890
    9900
    9910
    9920
    9930
    9940
    9950
    9960
    9970
    9980
    9990
    10000
    10010
    10020
    10030
    10040
    10050
    10060
    10070
    10080
    10090
    10100
    10110
    10120
    10130
    10140
    10150
    10160
    10170
    10180
    10190
    10200
    10210
    10220
    10230
    10240
    10250
    10260
    10270
    10280
    10290
    10300
    10310
    10320
    10330
    10340
    10350
    10360
    10370
    10380
    10390
    10400
    10410
    10420
    10430
    10440
    10450
    10460
    10470
    10480
    10490
    10500
    10510
    10520
    10530
    10540
    10550
    10560
    10570
    10580
    10590
    10600
    10610
    10620
    10630
    10640
    10650
    10660
    10670
    10680
    10690
    10700
    10710
    10720
    10730
    10740
    10750
    10760
    10770
    10780
    10790
    10800
    10810
    10820
    10830
    10840
    10850
    10860
    10870
    10880
    10890
    10900
    10910
    10920
    10930
    10940
    10950
    10960
    10970
    10980
    10990
    11000
    11010
    11020
    11030
    11040
    11050
    11060
    11070
    11080
    11090
    11100
    11110
    11120
    11130
    11140
    11150
    11160
    11170
    11180
    11190
    11200
    11210
    11220
    11230
    11240
    11250
    11260
    11270
    11280
    11290
    11300
    11310
    11320
    11330
    11340
    11350
    11360
    11370
    11380
    11390
    11400
    11410
    11420
    11430
    11440
    11450
    11460
    11470
    11480
    11490
    11500
    11510
    11520
    11530
    11540
    11550
    11560
    11570
    11580
    11590
    11600
    11610
    11620
    11630
    11640
    11650
    11660
    11670
    11680
    11690
    11700
    11710
    11720
    11730
    11740
    11750
    11760
    11770
    11780
    11790
    11800
    11810
    11820
    11830
    11840
    11850
    11860
    11870
    11880
    11890
    11900
    11910
    11920
    11930
    11940
    11950
    11960
    11970
    11980
    11990
    12000
    12010
    12020
    12030
    12040
    12050
    12060
    12070
    12080
    12090
    12100
    12110
    12120
    12130
    12140
    12150
    12160
    12170
    12180
    12190
    12200
    12210
    12220
    12230
    12240
    12250
    12260
    12270
    12280
    12290
    12300
    12310
    12320
    12330
    12340
    12350
    12360
    12370
    12380
    12390
    12400
    12410
    12420
    12430
    12440
    12450
    12460
    12470
    12480
    12490
    12500
    12510
    12520
    12530
    12540
    12550
    12560
    12570
    12580
    12590
    12600
    12610
    12620
    12630
    12640
    12650
    12660
    12670
    12680
    12690
    12700
    12710
    12720
    12730
    12740
    12750
    12760
    12770
    12780
    12790
    12800
    12810
    12820
    12830
    12840
    12850
    12860
    12870
    12880
    12890
    12900
    12910
    12920
    12930
    12940
    12950
    12960
    12970
    12980
    12990
    13000
    13010
    13020
    13030
    13040
    13050
    13060
    13070
    13080
    13090
    13100
    13110
    13120
    13130
    13140
    13150
    13160
    13170
    13180
    13190
    13200
    13210
    13220
    13230
    13240
    13250
    13260
    13270
    13280
    13290
    13300
    13310
    13320
    13330
    13340
    13350
    13360
    13370
    13380
    13390
    13400
    13410
    13420
    13430
    13440
    13450
    13460
    13470
    13480
    13490
    13500
    13510
    13520
    13530
    13540
    13550
    13560
    13570
    13580
    13590
    13600
    13610
    13620
    13630
    13640
    13650
    13660
    13670
    13680
    13690
    13700
    13710
    13720
    13730
    13740
    13750
    13760
    13770
    13780
    13790
    13800
    13810
    13820
    13830
    13840
    13850
    13860
    13870
    13880
    13890
    13900
    13910
    13920
    13930
    13940
    13950
    13960
    13970
    13980
    13990
    14000
    14010
    14020
    14030
    14040
    14050
    14060
    14070
    14080
    14090
    14100
    14110
    14120
    14130
    14140
    14150
    14160
    14170
    14180
    14190
    14200
    14210
    14220
    14230
    14240
    14250
    14260
    14270
    14280
    14290
    14300
    14310
    14320
    14330
    14340
    14350
    14360
    14370
    14380
    14390
    14400
    14410
    14420
    14430
    14440
    14450
    14460
    14470
    14480
    14490
    14500
    14510
    14520
    14530
    14540
    14550
    14560
    14570
    14580
    14590
    14600
    14610
    14620
    14630
    14640
    14650
    14660
    14670
    14680
    14690
    14700
    14710
    14720
    14730
    14740
    14750
    14760
    14770
    14780
    14790
    14800
    14810
    14820
    14830
    14840
    14850
    14860
    14870
    14880
    14890
    14900
    14910
    14920
    14930
    14940
    14950
    14960
    14970
    14980
    14990
    15000
    15010
    15020
    15030
    15040
    15050
    15060
    15070
    15080
    15090
    15100
    15110
    15120
    15130
    15140
    15150
    15160
    15170
    15180
    15190
    15200
    15210
    15220
    15230
    15240
    15250
    15260
    15270
    15280
    15290
    15300
    15310
    15320
    15330
    15340
    15350
    15360
    15370
    15380
    15390
    15400
    15410
    15420
    15430
    15440
    15450
    15460
    15470
    15480
    15490
    15500
    15510
    15520
    15530
    15540
    15550
    15560
    15570
    15580
    15590
    15600
    15610
    15620
    15630
    15640
    15650
    15660
    15670
    15680
    15690
    15700
    15710
    15720
    15730
    15740
    15750
    15760
    15770
    15780
    15790
    15800
    15810
    15820
    15830
    15840
    15850
    15860
    15870
    15880
    15890
    15900
    15910
    15920
    15930
    15940
    15950
    15960
    15970
    15980
    15990
    16000
    16010
    16020
    16030
    16040
    16050
    16060
    16070
    16080
    16090
    16100
    16110
    16120
    16130
    16140
    16150
    16160
    16170
    16180
    16190
    16200
    16210
    16220
    16230
    16240
    16250
    16260
    16270
    16280
    16290
    16300
    16310
    16320
    16330
    16340
    16350
    16360
    16370
    16380
    16390
    16400
    16410
    16420
    16430
    16440
    16450
    16460
    16470
    16480
    16490
    16500
    16510
    16520
    16530
    16540
    16550
    16560
    16570
    16580
    16590
    16600
    16610
    16620
    16630
    16640
    16650
    16660
    16670
    16680
    16690
    16700
    16710
    16720
    16730
    16740
    16750
    16760
    16770
    16780
    16790
    16800
    16810
    16820
    16830
    16840
    16850
    16860
    16870
    16880
    16890
    16900
    16910
    16920
    16930
    16940
```

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: IMAGE FORTBAN A CONVERSATIONAL MONITOR SYSTEM

```

C SEGM CARD
C 120 J=NTCHS(CARD,COL)
      IF(J.EQ. BLANK) GO TO 10
      COL=COL+1
      J=NUMBER(CARD,COL,SEG,0)
      GO TO 10
C PROCESSING DATE CARD
C 130 J=NTCHS(CARD,COL)
      IF(J.EQ. BLANK) GO TO 10
      COL=COL+1
      J=NUMBER(CARD,COL,PROCD,0)
      GO TO 10
C NPTS = NUMBER OF POINTS TO SKIP IN ANALYSIS
C 140 J = NUMBER(CARD,COL,CPTS,0)
      NPTS = CPTS - 1
      GO TO 10
C NPOS CARD, NUMBER OF DATA POSITIONS FROM WHICH TO OBTAIN DATA FOR
C CLASSY3.50 THAT THE DATA WILL BE SCRAMBLED
C 150 J=NUMBER(CARD,COL,NPOS,K0)
      GO TO 10
C SYMBOL CARD
C 170 I=NTCHS(CARD,COL)
      IF(I.EQ. BLANK) GO TO 10
      I=NUMBER(CARD,COL)
      IF(I.EQ. BLANK) GO TO 10
      IF(I.EQ. K0) GO TO 10
      SYM(I)=4
      GO TO 170
C PRINT OPTION CARD NO LONGER VALID
C 190 GO TO 10
C DATA FILE CARD
C 260 M = NTCHS(CARD,COL)
      IF(M.EQ. BLANK) GO TO 10
      IF(M.EQ. K0) GO TO 265
      IF(M.EQ. EPC) GO TO 267
      263 FORMAT(6,750)
      750 FORMAT(1, F030.0) ON DATA FILE CARD
      GO TO 10
      265 J = FIRST(CARD,COL,EQUIVFC)
      IF(J.EQ. BLANK) GO TO 264
      M = NUMBER(CARD,COL,DATADEF,750)
      COL = COL - 1
      GO TO 264
      267 J = FIRST(CARD,COL,EQUIVFC)
      IF(J.EQ. BLANK) GO TO 264
      M = NUMBER(CARD,COL,DATADEF,750)
      DATADEF = DATADEF - 1
      IF(DATADEF.EQ. 0) DATADEF = 0
      COL = COL - 1
      GO TO 260
C ITERATION CARD
C 270 J = NTCHS(CARD,COL)
      IF(J.EQ. BLANK) GO TO 10
      COL = COL - 1
      K = NUMBER(CARD,COL,TEMP,K0)
      NDCYC = TEMP(1)
      GO TO 10
C MAP CARD--WAY SPECIFY SERIES OF ITERATIONS TO BE MAPPED OR *ALL*
C 300 EXAMPLES: 1,3,5,7,9
      DO 301 I = 1,10
      301 MAP(I) = 0
      J = NTCHS(CARD,COL)
      IF(J.EQ. BLANK) GO TO 10
      IF *ALL* WAS REQUESTED, GO READ NEXT CARD
      C IF *ALL* WAS REQUESTED, GO READ NEXT CARD

```


FILE: Image

[illegible]

FILE: MAXLAFL FORTMAN A CONVERSATIONAL MONITOR SYSTEM

```

110 DO 110 J = 1, NOCC
    BETAL(L, J) = 1. / NOCAT
    CONTINUE
110 CONTINUE
-----BEGINNING OF ITERATIVE LOOP-----
200 CONTINUE
C SAVE OLD BETA VALUES FOR COMPARISON LATER
DO 210 I = 1, NOCC
    DO 210 J = 1, NOCAT
        BETAL(L, J) = BETAL(L, J)
210 CONTINUE
C CALC. ALL P(X, I) VALUES FOR ALL NOT DATA-CLUSTER COMBINATIONS
CALL ALPHAP
C CALC. PRODUCTS FOR ALL PRIOR EST (BETAL), CLASS REL PROP. (RELPPP),
AND CLASS CONDITIONAL PROBABILITIES (P(X, I))
C CALC. S(L, K) AS SUM OF (BETA*ALPHAP*(X, I)) / SUM ALL BETAL*ALPHAP*(X, I)
FOR ALL CLUSTERS
CALL HAVLS
C RE-CALCULATE BETAS, SET TO 0. IF LESS THAN .01
DO 300 K = 1, NOCC
    DO 300 I = 1, NOCAT
        BETAL(L, K) = S(L, K) / SK(K)
        IF (BETAL(L, K) .LT. .01) BETAL(L, K) = 0.
300 CONTINUE
C PRINT THE CURRENT VALUE OF THE LIKELIHOOD FUNCTION
CCCC CALL CALFCT
CCCC
C FIND LARGEST DIFFERENCE IN OLD AND NEW BETAS
XMAX = 0.
DO 500 J = 1, NOCC
    DO 500 I = 1, NOCAT
        ABSDIF = BETAL(L, J) - BETAL(L, J)
        IF (ABSDIF .GT. XMAX) XMAX = ABSDIF
500 CONTINUE
C PRINT BETAS
600 CONTINUE
WRITE (IOUT, 634) IOUTER
WRITE (IOUT, 605)
FORCAT (IOUT, 610) (I, J, BETAL(L, J), L=1, NOCAT), J=1, NOCC
605 WRITE (IOUT, 610) (I, J, CLASS, CLUST, BETAL(L, J))
610 FORCAT (I, J, 13, 5X, I3, 5X, F10.7)
C PRINT ESTIMATE FOR EACH LABELED CLASS WHERE EST = SUM (BETA * ALPHA)
CALL ESTIM
C PRINT LABELED CLUSTER MAP WHERE LABEL = MAX (BETA*ALPHAP*(X, I))
CCCC CALL PATHAP
C PRINT MAXIMUM CLASS FOR EACH CLUSTER
DO 630 I = 1, NOCC
C SAVE CLASS AND CLUSTER LABELS FOR MAXIMUM BETAS
CSTMAX = 0.
CSSLK = 0.
JCSS(K) = 0
LCLCSS(K) = 0
LCLCSS(K) = 0
DO 630 I = 1, NOCAT
    IF (BETAL(L, K) .GT. CSTMAX) GO TO 620
    LCLCSS(K) = LCLCSS(K)
    CSTMAX = BETAL(L, K)
    IF (BETAL(L, K) .GT. CSSMAX) GO TO 630
    JCSS(K) = LCLCSS(K)
    CSSMAX = BETAL(L, K)
630 CONTINUE

```


FILE: MAXLARFL FORTYAN A

```

C 100 CONTINUE
C
C      END OF DOT DATA PIVELS
C      END OF ONE CLASSY CLUSTER
C
C 500 RETURN
C      END
C      SUBROUTINE CALFCT
C
C      PURPOSE: CALC.  $\beta$ ETA*ALPHA*P(K,I) FOR EACH DOT-CLASS-CLUSTER COMBINATIONS
C
C      COMMON NO, NOCC, NOCAL, ITOTDT, MDP4, MDS, ICC,
C      1 TCDTDT, TDOUT, TDUT, CATNAM(20), DCON,
C      2 TDOTS(20,20), CVOLPT, PLPPT(30), CMELMS(16), CVRTN(15H),
C      3 PX(30,20), PAP(30), TDOTD(14), LABELS(30), LHLCST(30),
C      4 BETA(20,20), DBETA(20,30), SLK(20,30), SK(20,30), LHLCS, LHLCS1(30)
C      LOGICAL*1 LABELS, LHLCS, LHLCS1
C
C      WRITE HEADNG
C      WRITE (UNIT,410)
C      410 FORMAT(//, 'CATEGORY NAME CLUSTER NO. BETA RELPROP PX(K,I)
C      1 FCT FCTLK(K)')
C      FCTLK = 1.
C
C      PROCESS EACH DOT DATA POINT
C      DO 450 I = 1, ITOTDT
C      L = TDOTS(4,I)
C
C      PROCESS CLUSTER
C      FCT = 0.
C      DO 440 K = 1, NOCC
C      HELPRP = PLPPT(K)
C      FCT = BETA(L,K) * HELPRP * PX(K,I) + FCT
C      CONTINUE
C      440
C      FCTLK = FCTLK * FCT
C      CONTINUE
C      450
C      PRINT LIKE-LINE DOT FACTOR
C      WRITE (UNIT,460) FCTLK
C      460 FORMAT (' LIKE-LINE DOT FUNCTION = ',E12.3)
C      RETURN
C      END
C      SUBROUTINE MAPLS
C
C      PURPOSE: SUM PRODUCTS IN A CLASS FOR ALL DOT-CLUSTER COMBINATIONS
C
C      COMMON NO, NOCC, NOCAL, ITOTDT, MDP4, MDS, ICC,
C      1 TCDTDT, TDOUT, TDUT, CATNAM(20), DCON,
C      2 TDOTS(20,20), CVOLPT, PLPPT(30), CMELMS(16), CVRTN(15H),
C      3 PX(30,20), PAP(30), TDOTD(14), LABELS(30), LHLCST(30),
C      4 BETA(20,20), DBETA(20,30), SLK(20,30), SK(20,30), LHLCS, LHLCS1(30)
C      LOGICAL*1 LABELS, LHLCS, LHLCS1
C
C      TDOUT
C      NOCC
C      NOCAL
C      7E20 ACCUMULATORS
C      DO 10 I = 1, NOCAT
C      DO 10 K = 1, NOCC
C      SK(K) = 0.
C      SLK(L,K) = 0.0
C
C      PROCESS FOR EACH DOT
C      DO 100 IS = 1, ITOTDT
C      L = TDOTS(4,IS)
C      SUM = 0.0
C
C      ACCUMULATE FOR CURRENT CLUSTER FOR ALL DOT-CLASS COMBINATIONS
C      DO 100 K = 1, NOCC
C      PAP(K) = BETA(L,K) * HELPRP(K) * PX(K,I)
C      SUM = SUM + PAP(K)
C      100
C
C      SUM PAP'S FOR LABELLED CLASS-CLUSTER COMBINATIONS
C      DO 200 K = 1, NOCC

```

ORIGINAL PAGE IS
OF POOR QUALITY

CONFIRMATIONAL MONITOR SYSTEM

FILE: MAXLAKI FORMAN A

```

C  QUOT = MAP(K) / SUM
C  SK(L,K) = SK(L,K) + QUOT
C  SUM MAPS FOR LABELLED CLASSES
C  SK(K) = SK(K) + QUOT
200 CONTINUE
C 1000 CONTINUE
C  RETURN
C  SUBROUTINE PDELA
C  PURPOSE: PRINT ESTIMATE FOR EACH LABELLED CLASS
C  COMMON MC, NOCC, NOCAT, TOTUT, TOTPA, MDS, ICC,
C  1 TOTUT, TOTUT, TOTUT, CATMAP(20), OCON,
C  2 TOTUT(20,20), CVOLUT, CVOLUT(30), CMEDANS(16), CUVIN(158),
C  3 PX(30,200), MAP(40), TOTUT(16), LABELS(30), LHCSS(30),
C  4 HETA(20,30), OHEFA(20,30), SK(20,30), SK(30), LHCST(30)
C  LOGICAL*1 LABELS, LHCSS, LHCST
C  WRITE HEADING
C  WRITE (TOTUT,10)
C 10 FORMAT(//////, ESTIMATE = HETA * ALPHA, //, , CLASS ESTIMATE)
C  DO 100 I = 1, NOCAT
C  SUM = 0
C  DO 50 K = 1, NOCC
C  SUM = SUM + HETA(L,K) * PLPRP(K)
C 50 CONTINUE
C  WRITE ESTIMATE
C  WRITE (TOTUT,40) L, SUM
C 60 FORMAT (14,17,3X,F10.7)
C 100 CONTINUE
C  RETURN
C  SUBROUTINE DOTMAP
C  PURPOSE: POINT LABELLED CLUSTER MAP FOR EACH CLASS-CLUSTER
C  PIXEL CLUSTER = MAX(METAPLPHAP(X,I))
C  COMMON MC, NOCC, NOCAT, TOTUT, TOTPA, MDS, ICC,
C  1 TOTUT, TOTUT, TOTUT, CATMAP(20), OCON,
C  2 TOTUT(20,20), CVOLUT, CVOLUT(30), CMEDANS(16), CUVIN(158),
C  3 PX(30,200), MAP(40), TOTUT(16), LABELS(30), LHCSS(30),
C  4 HETA(20,30), OHEFA(20,30), SK(20,30), SK(30), LHCST(30)
C  LOGICAL*1 LABELS, LHCSS, LHCST
C  COMMON /MPXL/ MPXLA (19,11)
C  LOGICAL*1 MPXLA
C  LOGICAL*1 KLINK
C  DATA KLINK / , , /
C  WRITE (TOTUT,10)
C 10 FORMAT (11 PIXEL LABELLED DOT MAP , //, ,
C  1 , , 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18
C  2 19 , //)
C  DO 20 I = 1, 19
C  DO 20 J = 1, 11
C  MPXLAT(I,J) = KLINK
C  FIND MAX FOR EACH DOT
C  DO 200 N = 1, TOTUT
C  IX = TOTUTS (1,0) / 10
C  IY = TOTUTS (2,0) / 10
C  MPXMAX = 0
C 200 CONTINUE
C  CLASSES
C  DO 200 I = 1, NOCAT
C  PIXEL = 0
C  CLUSTERS
C  DO 100 I = 1, NOCC
C  PIXEL = PIXEL + HETA(L,I) * MPXLAT(I,J) * PX(I,0)
C  IF (PIXEL .GT. MPXMAX) MPXMAX = PIXEL
C  IF (PIXEL .GT. MPXMAX) MPXMAX = PIXEL
C  CONTINUE
C 200 CONTINUE
C 210 WRITE (TOTUT,210) (J, (MPXLA(I,J), I=1,19), J=1,11)
C  RETURN

```


FILE: MAXLARKI FORTRAN A CONVEFSATIONAL MODIOW SYSTEM

A-30

FILE: MAXLAREL FORTRAN A

CONVENTIONAL MONITOR SYSTEM

```

C
C  GO TO 10
C  END OF CLAY FILE
C 500  NOCC = NOCC - 1
      WRITE (IOUT,410)
      FORMAT (1000000)
      RETURN
C 600  WRITE (IOUT,410)
      FORMAT (1000000)
C 610  NOCC = NOCC - 1
      RETURN
      END
      SUBROUTINE GETCC
C
C  PURPOSE: Fill ONE SET OF CLAY VALUES USING 'ICC' AS AN INDEX
C
      COMMON NO, NOCC, NOCAT, ITOIT, TOT, CATNA(20), DOUT,
1  IOUT, TOT, NOCC, NOCAT, ITOIT, TOT, CATNA(20), DOUT,
2  TOT(20,20), CATNA(20), DOUT, TOT(20,20), CATNA(20), DOUT,
3  CATNA(20,20), CATNA(20), DOUT, TOT(20,20), CATNA(20), DOUT,
4  CATNA(20,20), CATNA(20), DOUT, TOT(20,20), CATNA(20), DOUT,
      LOGICAL LARLS, LARLS, LARLS, LARLS, LARLS, LARLS, LARLS, LARLS,
      COMMON/CLAY/ CC(15,15,30), CC(15,15,30), CC(15,15,30), CC(15,15,30),
      RELPRP = RELPRP(ICC)
C
C  CVOLEPT = CVOLEPT(ICC)
C
C  DO 10 I = 1,15
      CCFANS(I) = COMENS(I,ICC)
C 10
      DO 20 J = 1,15
      CVRIN(I) = CC(15,15,30)
      DCON = DCON(ICC)
C 20
      RETURN
      END
      FUNCTION DOTSOK (NO,V,AMET)
C
C  CALCULATES THE INNER PRODUCT V.V RELATIVE TO THE METRIC AMET
      REAL V(30), AMET(475)
      DEAL * DOTSOK(0.0)
C
      DOTSOK = 0.0
      DOTSOK = V(1)*V(1)*AMET(1)
      DO 10 I = 2,30
      IX = (I-1)*NO
      DO 8 J = 2,1
      DOTSOK = DOTSOK + V(I)*V(J-1)*AMET(MX+J-1)
      DOTSOK = DOTSOK + V(I)*V(1)*AMET(MX+1)
C 10
      THE DIAGONAL ELEMENTS ARE HANDLED SEPARATELY BECAUSE EACH OFF-
      DIAGONAL APPEARS TWICE, AND SO MUST BE DOUBLED.
      DOTSOK = DOTSOK + DOTSOK*DOTSOK
      RETURN
      END

```

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: WPTINS FORTAAN A CONVERSATIONAL MONITOR SYSTEM

```

C SUBROUTINE WPTINS
C PURPOSE: TO READ RADIANCE VALUES FOR LINES OF ORIGINAL PIXEL DATA
C           TO PRINT HEADING FOR REPORTS, TO CALL SUBROUTINES TO
C           CALCULATE REPORT DATA
C COMMON M0
C COMMON /TAPERF/ IINETP(196)
C COMMON /PXLIN/ N0PXL, LINE0, IINENO, IINFIN, IEND, PXLN(30,196),
C           IINDOIS(20,196), LINE(196), IFSTCL, LSTCOL, LSTP61, IFSTP2, LNSZP1, LNSZP2
C LOGICAL CAL*1 LINE
C COMMON /FILE/ DATFIL, MAPOPT
C DIMENSION ICOL(196,3)
C DATA KONSTR /PI*, KONSTC/C,
C DATA ISIZHD/4, IHEIGHT/8, ININE/9, ILEN/10/
C RADIANCE INFORMATION FOR LINES ON UNIT 24
C IUNIT = 24
C DEWING IUNIT
C GENERATE COLUMN HEADINGS
C DO 10 I = 1,196
C   ICOL(I,1) = 1/100
C   ICOL(I,2) = MOD(I,100)/10
C   ICOL(I,3) = MOD(I,10)
C 10
C READ NUMBER OF CHANNELS, FIRST AND LAST COLUMNS TO MAP
C IFSTC1 = 1
C LSTC1 = 196
C LSTLEN = 117
C CALCULATE PAGE LIMITS
C LSTP61 = IFSTC1 + 109
C IFSTP2 = LSTP61 + 1
C IF (LSTCOL - LSTP61) LSTP61 = LSTCOL
C CALCULATE LINE SIZE FOR HEADINGS AND TEXT
C LNSZP1 = (LSTP61 - IFSTP1 + 14) / 4
C LNSZP2 = (LSTCOL - IFSTP2 + 14) / 4
C HEADING--PAGE 1-- REPORT 1
C WRITE (6,15)
C FORMAT (14,1) PIXEL LABELLED CLUSTER MAP %/, 14,36X)
C WRITE (6,30) ((ICOL(I,J), I=IFSTC1, LSTP61), J=1,3)
C WRITE (6,31)
C HEADING--PAGE 2-- REPORT 1
C IF (IFSTP2 - LSTCOL) GO TO 160
C WRITE (25,15) ININE, ININE
C WRITE (25,16) LNSZP2, (ICOL(I,1), I=IFSTP2, LSTCOL)
C WRITE (25,17) LNSZP2, (ICOL(I,2), I=IFSTP2, LSTCOL)
C WRITE (25,18) LNSZP2, (ICOL(I,3), I=IFSTP2, LSTCOL)
C WRITE (25,31) IHEIGHT
C WRITE HEADER FOR UNIVERSAL FILE, IF PIXEL OR CLUSTER MAP REQUESTED
C IF (MAPOPT .NE. KONSTR .AND. MAPOPT .NE. KONSTC) GO TO 160
C IZERO = 0
C CALL FSEFEL(31, IZERO, IOUNNY)
C ICHAN = 1
C IPSAMP = 1
C IPEXT = 1
C CALL WPTHD (ICHAN, ICHAN, IPSAMP, IPEXT, 31)
C HEADING--PAGE 1-- REPORT 2
C WRITE (25, 610) IUNIT, IHEIGHT
C FORMAT (14,1) CLUSTER LABELLED CLUSTER MAP %/, 14, 32X)
C WRITE (25,32) (LNSZP1, I=IFSTC1, LSTP61), J=1,3)
C WRITE (25,31) ISIZHD
C

```

FILF: WDTLNS FORTAN A CONVERSATIONAL MONITOR SYSTEM

```

C  HEADING--PAGE 2. REPORT 2
  IF (IFSTP2.GT. LSTCOL) GO TO 140
  WRITE (27.41) LINE. I(16-1)
  WRITE (27.41) ISI/HO
  WRITE (27.41) LNS/P2. (ICOL(1.1).I=IFSTP2.LSTCOL)
  WRITE (27.41) LNS/P2. (ICOL(1.2).I=IFSTP2.LSTCOL)
  WRITE (27.41) LNS/P2. (ICOL(1.3).I=IFSTP2.LSTCOL)
  WRITE (27.41) ISI/HO

C  HEADING PAGE 1. REPORT 3
  WRITE (28.62) ISI/HO. ISI/HO
  FORMAT (14.32) UNLAFLED CLUSTER MAP :/:14.32X
  WRITE (28.32) LNS/P1. (ICOL(1.1).I=IFSTCL.LSTPGL),J=1.3
  WRITE (28.31) ISI/HO

C  HEADING PAGE 2. REPORT 3
  IF (IFSTP2.GT. LSTCOL) GO TO 200
  WRITE (29.42) ISI/HO. ISI/HO
  WRITE (29.32) LNS/P2. (ICOL(1.1).I=IFSTP2.LSTCOL)
  WRITE (29.32) LNS/P2. (ICOL(1.2).I=IFSTP2.LSTCOL)
  WRITE (29.32) LNS/P2. (ICOL(1.3).I=IFSTP2.LSTCOL)
  WRITE (29.31) ISI/HO
  FORMAT (14.32X)
  FORMAT (14.10X.11011)

C  READ RADIANCE VALUES
  NOTAP = 0
  200 1 DEAD (LIMIT. FND=240) NORALV. LINEO. IREGIN. IFND.
    IF (LINEO.FQ. LSTLNE) NOTAP = 1
    IF (LINEO.FQ. LSTLNE) NOTAP = 1

    CALL PXILN
    CALL LNHAP

C  WRITE UNIVERSAL TAPE IF 'PIXEL' MAP REQUESTED
  IF (MAPINT.FQ. KUNSTP) CALL WRTLN (LINEP. NOTAP)

C  CALL LNHAP

C  WRITE UNIVERSAL TAPE IF 'CLUSTER' MAP REQUESTED
  IF (MAPINT.FQ. KUNSTC) CALL WRTLN (LINEP. NOTAP)
  CALL LNHAP

C  GO TO 240

C  PRINT REPORTS THAT HAVE BEEN COLLECTED
  240 IF (IFSTP2.GT. LSTCOL) GO TO 260
  CALL PAGE(25)

C  REPORT 2
  260 CALL PAGE(26)
  IF (IFSTP2.GT. LSTCOL) GO TO 280
  CALL PAGE(27)

C  REPORT 3
  280 CALL PAGE(28)
  IF (IFSTP2.GT. LSTCOL) GO TO 300
  CALL PAGE(29)

C  RETURN
  300 RETURN

C  NO DATA ON FILE
  2000 WRITE (5. 2010)
  2010 FORMAT (' NO DATA ON FILE 24')
  STOP
  ENH
  SUBROUTINE PXILN

C  PURPOSE: CALCULATE THE PROBABILITY OF X (DOT DATA PIXEL) GIVEN
C  I (CLAY CLUSTER) FOR EACH X IN THE LINE IN THE IMAGE FILE
C  PIX.I) IS BASED ON RELATIONSHIP BETWEEN DOT DATA PTS AND CLUSTERS
C  COMMON MO. NOCC. NOCAT. ITOTDT. MOP4. MOS. ICC.

```

```

1 ICLUNT, ICLUNT, ICLUNT, CATNA(120), DCON,
2 IDOTS(20,20), CVOLRT, PLPRT(30), CMEANS(16), CVRIN(158),
3 PX(30,20), MAP(30), DOTDT(16), LABELS(30), LHLCS(30),
4 BETA(20,30), ORFIA(20,30), SLK(20,30), SK(30), LHLCS(30),
  LOGICAL*1 LABELS, LHLCS, LHLCS

COMMON /PX,LY, NXPAL, LINE(196), IFSTCL, LSTCOL, LSTP2, LNSZP1, LNSZP2,
  LOGICAL*1 LINE

DIMENSION DIFX(4)(8)

PX = PROBABILITY OF EACH DOT DATA PIXEL GIVEN CLASY CLUSTER
ICLUNT = NUMBER OF DOT DATA PIXELS
NOCCL = NUMBER OF CLASY CLUSTERS
IDOTS = DOT DATA PIXEL ARRAY
ICLUNT = CLASY FILE UNIT
MO = NUMBER OF CHANNELS
MOS = NUMBER OF ELEMENTS IN TRIANGULARIZED ARRAY

*** CALCULATE P(X,I) FOR EACH OF THE CLASY CLUSTERS
DO 100 I = 1, NOCC
  ICC = I
  CALL GETCC

READ CLASY RELATIVE PROP, VOLRT, MEANS, AND CO-VARIANCE INVERSE MATRIX
CALL GETCC

PROCESS DOT DATA PIXELS
DO 100 IPXL = IHEGIN, IFEND

CALCULATE DIFFERENCE IN SPECTRAL VALUES
DO 30 J = 1, MO
  DIFXMN(J) = LNDOTS(J, IPXL) - CMEANS(J)
CONTINUE

CALCULATE PRODUCT
PRODUCT = DOTSK (MO, DIFXMN, CVRIN)

CALCULATE P(X,I) VALUE FOR CURRENT CLASY CLUSTER
IF (PRODUCT, LT, 150.) PXLN = (EXP(-PRODUCT/2.)) * (EXP(-DCON/2.)) / CVOLRT
IF (PRODUCT, GE, 150.) PXLN = 0.0
PXLN(I, IPXL) = PXLN

100 CONTINUE
END OF DOT DATA PIXELS
END OF ONE CLASY CLUSTER

500 GETUP1
END
SUBROUTINE LINEAP
PURPOSE: PRINT LABELED CLUSTER MAP FOR EACH CLASS-CLUSTER
  PIXEL CLUSTER = MAX(BETA*ALPHA*P(X,I))

COMMON /MO, NOCC, NOCAT, ITOTDT, MJP4, MJS, ICC,
1 ICLUNT, ICLUNT, ICLUNT, CATNA(20), DCON,
2 IDOTS(20,20), CVOLRT, PLPRT(30), CMEANS(16), CVRIN(158),
3 PX(30,20), MAP(30), DOTDT(16), LABELS(30), LHLCS(30),
4 BETA(20,30), ORFIA(20,30), SLK(20,30), SK(30), LHLCS(30),
  COMMON /TAP, RE, LINE(196), LHLCS, LHLCS
  LOGICAL*1 LABELS, LHLCS, LHLCS

COMMON /PX,LY, NXPAL, LINE(196), IFSTCL, LSTCOL, LSTP2, LNSZP1, LNSZP2,
  LOGICAL*1 LINE
COMMON /MJPXL, MAPPXL(209)

LOGICAL*1 IHLPIK
DATA IHLNK /% /
DATA ISITH /5/

FIND MAX FOR EACH DOT
DO 50 I = IHEGIN, IFEND
  
```

FILF: WPTLNS FORTRAN A CONVERSATIONAL MONITOR SYSTEM

```

50 LINE(I) = IHLNK
C SET LAST LINE SWITCH TO 'NOT LAST'
C
C CLASSES
DO 200 N = IBEGIN, IEND
  PXLMAX = 0
  DO 200 L = 1, NOCAT
    PXL = 0
    C CLUSTERS
    DO 100 I = 1, NOCC
      PXL = PXL + META(L, I) * RLPP(I) * PXLN(I, N)
      IF (PXL .LE. PXLMAX) GO TO 200
    END DO
    LINF(N) = LAFSL(L)
    LINF(N) = L
    PXLMAX = PXL
  END DO
  CONTINUE
200
C WRITE PAGE 1
WRITE (4, 209) (LINE(I), (LINE(I), I=IFSTCL, LSTPG1))
209 FORMAT (1X, 14, 5X, 110A1)
210
C SAVE PAGE 2 ON UNIT 25 IF THERE IS A PAGE 2
IF (IFSTP2 .LE. LSTCOL) WRITE (25, 210)
1 LNSZP2, LINE(I), I=IFSTP2, LSTCOL
C RETURN
END
C SUBROUTINE LMAP
C PURPOSE: PRINT LABELED CLUSTER MAP FOR EACH LINE
C PXL CLUSTER LABEL = MAX (ALPHA * P(X, I))
C
COMMON MO, NOCC, NOCAT, ITOTD, MOP4, MDS, ICC,
1 ICLINT, ICLINT, IOUT, CATNAM(20), DCON,
2 IDOTS(20, 20), CVOLRT, RLPP(30), CMEANS(16), CVRIN(158),
3 PX(30, 20), XZ(30), DODT(16), LAHLS(30), LHLCS(30),
4 RETA(20, 30), OHETA(20, 30), SLK(20, 30), SK(30), LHLCS(30)
COMMON /TAPERF/ LINF(196)
C
LOGICAL *1 LABELS, LHLCS, LHLST
COMMON /PXLN/ NOPXL, LINE(I), I=IFSTCL, LSTPG1, IEND, PXLN(30, 196), LNSZP2
LNDOTS(20, 196), LINE(196), IFSTCL, LSTCOL, LSTPG1, IFSTP2, LNSZP1, LNSZP2
LOGICAL *1 LINE
C
LOGICAL *1 KBLNK
DATA KBLNK / 0, 0 /
C
DO 70 J = IBEGIN, IEND
  LINF(I) = KBLNK
70
C FIND MAX FOR EACH PIXEL ON LINE
DO 150 N = IBEGIN, IEND
  PXLMAX = 0
  C CLUSTERS
  DO 100 I = 1, NOCC
    PXL = RLPP(I) * PXLN(I, N)
    IF (PXL .LE. PXLMAX) GO TO 100
  END DO
  LINF(N) = LHLCS(I)
  LINF(N) = I
  PXLMAX = PXL
100 CONTINUE
150 CONTINUE
C
WRITE (28, 210) LNSZP1, LINE(I), I=IFSTCL, LSTPG1
210 FORMAT (14, 1X, 14, 5X, 110A1)
C
SAVE PAGE 2 IF THERE IS ONE
IF (IFSTP2 .LE. LSTCOL) WRITE (29, 210)
1 LNSZP2, LINE(I), I=IFSTP2, LSTCOL
C RETURN
END

```

ORIGINAL PAGE IS
OF POOR QUALITY

FILE: WPTLMS FORTRAN A CONVERSATIONAL MONITOR SYSTEM

```

C SURROUTINE LMAP2
C PURPOSE: PRINT LABELED CLUSTER MAP FOR EACH LINE
C PIXEL CLUSTER LABEL = MAX (ALPHA * P(Y,I))
COMMON M0, NOCC, NOCAT, IICDT, MOP4, M05, ICC,
1 ICI, IUT, IDO, IUT, CATNAM(20), DCON,
2 IDOTS(20,20), CVOLRT, RLPDP(30), CMEANS(16), CVIN(158),
3 PX(30,20), RAP(30), OYDT(14), LAHLS(30), LMLCSS(30),
4 RETAI(20,30), OBETA(20,30), SLK(20,30), SK(30), LBLCS(30),
/ LOGICAL*1 LAHLS, LRLCSS, LHLCS,
COMMON /PXLN/ NOPXL, LINE, IEND, IEGIN, IEND, PXLN(30,196),
1 LNDOTS(20,196), LINE(196), IFSTCL, LSTCOL, LSTP2, LNSZP1, LNSZP2,
LOGICAL*1 LINE
C
C LOGICAL*1 KRLNK
C DATA KRLNK/'.'/
C
C DO 70 I = IEGIN, IEND
C LINE(I) = KRLNK
C
C FIND MAX FOR EACH PIXEL ON LINE
C DO 150 N = IEGIN, IEND
C PXLMAX = 0.0
C
C CLUSTERS
C DO 100 I = 1, NOCC
C PIXEL = RLPDP(I) * PXLN(I,N)
C IF (PIXEL .GT. PXLMAX) LINE(N) = LBLCSS(I)
C IF (PIXEL .GT. PXLMAX) PXLMAX = PIXEL
C CONTINUE
C CONTINUE
C
C WRITE (26,210) LNSZP1, LINE, IEND, IEGIN, IEND, IEGIN, LSTP2, LSTCOL
C FORMAT (14,1X,14,5X,110A1)
C
C SAVE PAGE 2 IF THERE IS ONE
C IF (IFSTP2 .LE. LSTCOL) WRITE (27,210)
C 1 LNSZP2, LINE, IEND, IEGIN, IEND, IEGIN, LSTCOL
C
C RETURN
C END
C SURROUTINE PAGE(IUNIT)
C
C DIMENSION LINE(196)
C
C PURPOSE: READ DATA FOR PAGE FROM TEMPORARY FILE AND WRITE REPORT
C TITLE AND COLUMN HEADING PRINTED BY WRTLNS
C
C PRINT IUNIT
C
C PRINT IINFS OF REPORT
C 510 READ (IUNIT, 20, END=590) ISIZE, (LINE(I), I=1, ISIZE)
C 20 FORMAT (14,32A4)
C WRITE (6,30) (LINE(I), I=1, ISIZE)
C 30 FORMAT (33A4)
C GO TO 510
C
C REWIND IUNIT
C 590 RETURN
C END

```